Factory Boy Documentation

Release 2.8.1

Raphaël Barrois, Mark Sandstrom

December 17, 2016

Contents

1	Links	3			
2	Download	5			
3	Usage	7			
	3.1 Defining factories	7			
	3.2 Using factories	7			
	3.3 Realistic, random values	8			
	3.4 Lazy Attributes	8			
	3.5 Sequences	9			
	3.6 Associations	9			
	3.7 ORM Support	10			
	3.8 Debugging factory_boy	10			
4	Contributing	11			
5	5 Contents, indices and tables				
	5.1 Introduction	13			
	5.2 Reference	18			
	5.3 Using factory_boy with ORMs	44			
	5.4 Common recipes	51			
	5.5 Fuzzy attributes	58			
	5.6 Examples	63			
	5.7 Internals	65			
	5.8 ChangeLog	65			
	5.9 Ideas	74			
Py	ython Module Index	75			

factory_boy is a fixtures replacement based on thoughtbot's factory_girl.

As a fixtures replacement tool, it aims to replace static, hard to maintain fixtures with easy-to-use factories for complex object.

Instead of building an exhaustive test setup with every possible combination of corner cases, factory_boy allows you to use objects customized for the current test, while only declaring the test-specific fields:

```
class FooTests(unittest.TestCase):
   def test_with_factory_boy(self):
        # We need a 200€, paid order, shipping to australia, for a VIP customer
        order = OrderFactory(
           amount=200.
           status='PAID',
           customer__is_vip=True,
           address__country='AU',
        # Run the tests here
   def test_without_factory_boy(self):
        address = Address(
            street="42 fubar street",
            zipcode="42Z42",
            city="Sydney",
            country="AU",
        )
        customer = Customer(
            first_name="John",
           last_name="Doe",
           phone="+1234",
            email="john.doe@example.org",
            active=True,
            is_vip=True,
            address=address,
        )
```

factory_boy is designed to work well with various ORMs (Django, Mongo, SQLAlchemy), and can easily be extended for other libraries.

Its main features include:

- · Straightforward declarative syntax
- Chaining factory calls while retaining the global context
- Support for multiple build strategies (saved/unsaved instances, stubbed objects)
- Multiple factories per class support, including inheritance

Contents 1

2 Contents

CHAPTER 1

Links

- Documentation: https://factoryboy.readthedocs.io/
- Repository: https://github.com/FactoryBoy/factory_boy
- Package: https://pypi.python.org/pypi/factory_boy/
- Mailing-list: factoryboy@googlegroups.com | https://groups.google.com/forum/#!forum/factoryboy

factory_boy supports Python 2.7, 3.2 to 3.5, as well as PyPy; it requires only the standard Python library.

4 Chapter 1. Links

CHAPTER 2

Download

PyPI: https://pypi.python.org/pypi/factory_boy/

\$ pip install factory_boy

Source: https://github.com/FactoryBoy/factory_boy/

\$ git clone git://github.com/FactoryBoy/factory_boy/

\$ python setup.py install

Usage

Note: This section provides a quick summary of factory_boy features. A more detailed listing is available in the full documentation.

3.1 Defining factories

Factories declare a set of attributes used to instantiate an object. The class of the object must be defined in the model field of a class Meta: attribute:

```
import factory
from . import models

class UserFactory(factory.Factory):
    class Meta:
        model = models.User

    first_name = 'John'
    last_name = 'Doe'
    admin = False

# Another, different, factory for the same object
class AdminFactory(factory.Factory):
    class Meta:
        model = models.User

first_name = 'Admin'
    last_name = 'User'
    admin = True
```

3.2 Using factories

factory_boy supports several different build strategies: build, create, and stub:

```
# Returns a User instance that's not saved
user = UserFactory.build()
# Returns a saved User instance
```

```
user = UserFactory.create()
# Returns a stub object (just a bunch of attributes)
obj = UserFactory.stub()
```

You can use the Factory class as a shortcut for the default build strategy:

```
# Same as UserFactory.create()
user = UserFactory()
```

No matter which strategy is used, it's possible to override the defined attributes by passing keyword arguments:

```
# Build a User instance and override first_name
>>> user = UserFactory.build(first_name='Joe')
>>> user.first_name
"Joe"
```

It is also possible to create a bunch of objects in a single call:

```
>>> users = UserFactory.build_batch(10, first_name="Joe")
>>> len(users)
10
>>> [user.first_name for user in users]
["Joe", "Joe", "Joe", "Joe", "Joe", "Joe", "Joe", "Joe", "Joe"]
```

3.3 Realistic, random values

Demos look better with random yet realistic values; and those realistic values can also help discover bugs. For this, factory_boy relies on the excellent fake-factory library:

```
class RandomUserFactory(factory.Factory):
    class Meta:
        model = models.User

first_name = factory.Faker('first_name')
    last_name = factory.Faker('last_name')
```

```
>>> UserFactory()
<User: Lucy Murray>
```

Note: Use of fully randomized data in tests is quickly a problem for reproducing broken builds. To that purpose, factory_boy provides helpers to handle the random seeds it uses.

3.4 Lazy Attributes

Most factory attributes can be added using static values that are evaluated when the factory is defined, but some attributes (such as fields whose value is computed from other elements) will need values assigned each time an instance is generated.

These "lazy" attributes can be added as follows:

8 Chapter 3. Usage

```
class UserFactory(factory.Factory):
    class Meta:
        model = models.User

    first_name = 'Joe'
    last_name = 'Blow'
    email = factory.LazyAttribute(lambda a: '{0}.{1}@example.com'.format(a.first_name, a.last_name).date_joined = factory.LazyFunction(datetime.now)
```

```
>>> UserFactory().email
"joe.blow@example.com"
```

Note: LazyAttribute calls the function with the object being constructed as an argument, when LazyFunction does not send any argument.

3.5 Sequences

Unique values in a specific format (for example, e-mail addresses) can be generated using sequences. Sequences are defined by using Sequence or the decorator sequence:

```
class UserFactory(factory.Factory):
    class Meta:
        model = models.User

    email = factory.Sequence(lambda n: 'person{0}@example.com'.format(n))

>>> UserFactory().email
'person0@example.com'
>>> UserFactory().email
'person1@example.com'
```

3.6 Associations

Some objects have a complex field, that should itself be defined from a dedicated factories. This is handled by the SubFactory helper:

```
class PostFactory(factory.Factory):
    class Meta:
        model = models.Post
    author = factory.SubFactory(UserFactory)
```

The associated object's strategy will be used:

```
# Builds and saves a User and a Post
>>> post = PostFactory()
>>> post.id is None # Post has been 'saved'
False
>>> post.author.id is None # post.author has been saved
False
# Builds but does not save a User, and then builds but does not save a Post
```

3.5. Sequences 9

```
>>> post = PostFactory.build()
>>> post.id is None
True
>>> post.author.id is None
True
```

3.7 ORM Support

factory_boy has specific support for a few ORMs, through specific factory.Factory subclasses:

- Django, with factory.django.DjangoModelFactory
- Mogo, with factory.mogo.MogoFactory
- MongoEngine, with factory.mongoengine.MongoEngineFactory
- SQLAlchemy, with factory.alchemy.SQLAlchemyModelFactory

3.8 Debugging factory_boy

Debugging factory_boy can be rather complex due to the long chains of calls. Detailed logging is available through the factory logger.

A helper, *factory.debug()*, is available to ease debugging:

```
with factory.debug():
    obj = TestModel2Factory()

import logging
logger = logging.getLogger('factory')
logger.addHandler(logging.StreamHandler())
logger.setLevel(logging.DEBUG)
```

This will yield messages similar to those (artificial indentation):

```
BaseFactory: Preparing tests.test_using.TestModel2Factory(extra={})

LazyStub: Computing values for tests.test_using.TestModel2Factory(two=<OrderedDeclarationWrapper for SubFactory: Instantiating tests.test_using.TestModelFactory(__containers=(<LazyStub) for tests.test_BaseFactory: Preparing tests.test_using.TestModelFactory(extra={'__containers': (<LazyStub) for tests.test_using.TestModelFactory(one=4)

LazyStub: Computing values for tests.test_using.TestModelFactory(one=4)

BaseFactory: Generating tests.test_using.TestModelFactory(one=4)

LazyStub: Computed values, got tests.test_using.TestModel2Factory(two=<tests.test_using.TestModel object at BaseFactory: Generating tests.test_using.TestModel2Factory(two=<tests.test_using.TestModel object at
```

10 Chapter 3. Usage

Contributing

factory_boy is distributed under the MIT License.

Issues should be opened through GitHub Issues; whenever possible, a pull request should be included. Questions and suggestions are welcome on the mailing-list.

All pull request should pass the test suite, which can be launched simply with:

\$ make test

In order to test coverage, please use:

\$ make coverage

To test with a specific framework version, you may use:

\$ make DJANGO=1.9 test

Valid options are:

- DJANGO for Django
- MONGOENGINE for mongoengine
- ALCHEMY for SQLAlchemy

To avoid running mongoengine tests (e.g no mongo server installed), run:

\$ make SKIP_MONGOENGINE=1 test

Contents, indices and tables

5.1 Introduction

The purpose of factory_boy is to provide a default way of getting a new instance, while still being able to override some fields on a per-call basis.

Note: This section will drive you through an overview of factory_boy's feature. New users are advised to spend a few minutes browsing through this list of useful helpers.

Users looking for quick helpers may take a look at Common recipes, while those needing detailed documentation will be interested in the Reference section.

5.1.1 Basic usage

Factories declare a set of attributes used to instantiate an object, whose class is defined in the class Meta's model attribute:

- Subclass factory. Factory (or a more suitable subclass)
- Add a class Meta: block
- Set its model attribute to the target class
- Add defaults for keyword args to pass to the associated class' __init__ method

```
import factory
from . import base

class UserFactory(factory.Factory):
    class Meta:
        model = base.User

firstname = "John"
    lastname = "Doe"
```

You may now get base. User instances trivially:

```
>>> john = UserFactory()
<User: John Doe>
```

It is also possible to override the defined attributes by passing keyword arguments to the factory:

```
>>> jack = UserFactory(firstname="Jack")
<User: Jack Doe>
```

A given class may be associated to many Factory subclasses:

```
class EnglishUserFactory(factory.Factory):
    class Meta:
        model = base.User

    firstname = "John"
    lastname = "Doe"
    lang = 'en'

class FrenchUserFactory(factory.Factory):
    class Meta:
        model = base.User

    firstname = "Jean"
    lastname = "Dupont"
    lang = 'fr'
```

```
>>> EnglishUserFactory()
<User: John Doe (en)>
>>> FrenchUserFactory()
<User: Jean Dupont (fr)>
```

5.1.2 Sequences

When a field has a unique key, each object generated by the factory should have a different value for that field. This is achieved with the *Sequence* declaration:

```
class UserFactory(factory.Factory):
    class Meta:
        model = models.User

    username = factory.Sequence(lambda n: 'user%d' % n)
```

```
>>> UserFactory()
<User: user1>
>>> UserFactory()
<User: user2>
```

Note: For more complex situations, you may also use the @sequence() decorator (note that self is not added as first parameter):

```
class UserFactory(factory.Factory):
    class Meta:
        model = models.User

@factory.sequence
    def username(n):
        return 'user%d' % n
```

5.1.3 LazyFunction

In simple cases, calling a function is enough to compute the value. If that function doesn't depend on the object being built, use LazyFunction to call that function; it should receive a function taking no argument and returning the value for the field:

```
class LogFactory(factory.Factory):
    class Meta:
        model = models.Log

    timestamp = factory.LazyFunction(datetime.now)
```

```
>>> LogFactory()
<Log: log at 2016-02-12 17:02:34>
>>> # The LazyFunction can be overriden
>>> LogFactory(timestamp=now - timedelta(days=1))
<Log: log at 2016-02-11 17:02:34>
```

Note: For complex cases when you happen to write a specific function, the @lazy_attribute() decorator should be more appropriate.

5.1.4 LazyAttribute

Some fields may be deduced from others, for instance the email based on the username. The LazyAttribute handles such cases: it should receive a function taking the object being built and returning the value for the field:

```
class UserFactory(factory.Factory):
    class Meta:
        model = models.User

    username = factory.Sequence(lambda n: 'user%d' % n)
    email = factory.LazyAttribute(lambda obj: '%s@example.com' % obj.username)
```

```
>>> UserFactory()
<User: user1 (user1@example.com)>
>>> # The LazyAttribute handles overridden fields
>>> UserFactory(username='john')
<User: john (john@example.com)>
>>> # They can be directly overridden as well
>>> UserFactory(email='doe@example.com')
<User: user3 (doe@example.com)>
```

Note: As for Sequence, a @lazy_attribute() decorator is available:

```
class UserFactory(factory.Factory):
    class Meta:
        model = models.User

username = factory.Sequence(lambda n: 'user%d' % n)
```

5.1. Introduction 15

```
@factory.lazy_attribute
def email(self):
    return '%s@example.com' % self.username
```

5.1.5 Inheritance

Once a "base" factory has been defined for a given class, alternate versions can be easily defined through subclassing.

The subclassed Factory will inherit all declarations from its parent, and update them with its own declarations:

```
class UserFactory(factory.Factory):
    class Meta:
        model = base.User

    firstname = "John"
    lastname = "Doe"
    group = 'users'

class AdminFactory(UserFactory):
    admin = True
    group = 'admins'
```

```
>>> user = UserFactory()
>>> user
<User: John Doe>
>>> user.group
'users'
>>> admin = AdminFactory()
>>> admin
<User: John Doe (admin)>
>>> admin.group # The AdminFactory field has overridden the base field
'admins'
```

Any argument of all factories in the chain can easily be overridden:

```
>>> super_admin = AdminFactory(group='superadmins', lastname="Lennon")
>>> super_admin
<User: John Lennon (admin)>
>>> super_admin.group # Overridden at call time
'superadmins'
```

5.1.6 Non-kwarg arguments

Some classes take a few, non-kwarg arguments first.

This is handled by the <code>inline_args</code> attribute:

```
class MyFactory(factory.Factory):
    class Meta:
        model = MyClass
        inline_args = ('x', 'y')

    x = 1
    y = 2
    z = 3
```

```
>>> MyFactory(y=4)
<MyClass(1, 4, z=3)>
```

5.1.7 Altering a factory's behaviour: parameters and traits

Some classes are better described with a few, simple parameters, that aren't fields on the actual model. In that case, use a Params declaration:

```
class RentalFactory(factory.Factory):
    class Meta:
        model = Rental

    begin = factory.fuzzy.FuzzyDate(start_date=datetime.date(2000, 1, 1))
    end = factory.LazyAttribute(lambda o: o.begin + o.duration)

class Params:
    duration = 12
```

```
>>> RentalFactory(duration=0)

<Rental: 2012-03-03 -> 2012-03-03>

>>> RentalFactory(duration=10)

<Rental: 2008-12-16 -> 2012-12-26>
```

When many fields should be updated based on a flag, use Traits instead:

```
class OrderFactory(factory.Factory):
    status = 'pending'
    shipped_by = None
    shipped_on = None

class Meta:
    model = Order

class Params:
    shipped = factory.Trait(
        status='shipped',
        shipped_by=factory.SubFactory(EmployeeFactory),
        shipped_on=factory.LazyFunction(datetime.date.today),
    )
```

A trait is toggled by a single boolean value:

```
>>> OrderFactory()
<Order: pending>
>>> OrderFactory(shipped=True)
<Order: shipped by John Doe on 2016-04-02>
```

5.1.8 Strategies

All factories support two built-in strategies:

- build provides a local object
- create instantiates a local object, and saves it to the database.

5.1. Introduction 17

Note: For 1.X versions, the create will actually call AssociatedClass.objects.create, as for a Django model.

Starting from 2.0, factory.Factory.create() simply calls AssociatedClass(**kwargs). You should use DjangoModelFactory for Django models.

When a Factory includes related fields (SubFactory, RelatedFactory), the parent's strategy will be pushed onto related factories.

Calling a Factory subclass will provide an object through the default strategy:

```
class MyFactory(factory.Factory):
    class Meta:
        model = MyClass
```

```
>>> MyFactory.create()
<MyFactory: X (saved)>
>>> MyFactory.build()
<MyFactory: X (unsaved)>
>>> MyFactory() # equivalent to MyFactory.create()
<MyClass: X (saved)>
```

The default strategy can be changed by setting the class Meta strategy attribute.

5.2 Reference

This section offers an in-depth description of factory_boy features.

For internals and customization points, please refer to the Internals section.

5.2.1 The Factory class

Meta options

```
class factory.FactoryOptions
```

New in version 2.4.0.

A Factory's behaviour can be tuned through a few settings.

For convenience, they are declared in a single class Meta attribute:

```
class MyFactory(factory.Factory):
    class Meta:
        model = MyObject
        abstract = False
```

model

This optional attribute describes the class of objects to generate.

If unset, it will be inherited from parent *Factory* subclasses.

New in version 2.4.0.

abstract

This attribute indicates that the *Factory* subclass should not be used to generate objects, but instead provides some extra defaults.

It will be automatically set to True if neither the Factory subclass nor its parents define the model attribute.

Warning: This flag is reset to False when a Factory subclasses another one if a model is set.

New in version 2.4.0.

inline_args

Some factories require non-keyword arguments to their __init__(). They should be listed, in order, in the <code>inline_args</code> attribute:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User
        inline_args = ('login', 'email')

login = 'john'
    email = factory.LazyAttribute(lambda o: '%s@example.com' % o.login)
    firstname = "John"
```

New in version 2.4.0.

exclude

While writing a Factory for some object, it may be useful to have general fields helping defining others, but that should not be passed to the model class; for instance, a field named 'now' that would hold a reference time used by other objects.

Factory fields whose name are listed in *exclude* will be removed from the set of args/kwargs passed to the underlying class; they can be any valid factory_boy declaration:

```
class OrderFactory(factory.Factory):
    class Meta:
        model = Order
        exclude = ('now',)

        now = factory.LazyFunction(datetime.datetime.utcnow)
        started_at = factory.LazyAttribute(lambda o: o.now - datetime.timedelta(hours=1))
        paid_at = factory.LazyAttribute(lambda o: o.now - datetime.timedelta(minutes=50))
```

```
>>> OrderFactory()  # The value of 'now' isn't passed to Order()
<Order: started 2013-04-01 12:00:00, paid 2013-04-01 12:10:00>
>>> # An alternate value may be passed for 'now'
>>> OrderFactory(now=datetime.datetime(2013, 4, 1, 10))
<Order: started 2013-04-01 09:00:00, paid 2013-04-01 09:10:00>
```

New in version 2.4.0.

rename

Sometimes, a model expects a field with a name already used by one of Factory's methods.

In this case, the *rename* attributes allows to define renaming rules: the keys of the *rename* dict are those used in the *Factory* declarations, and their values the new name:

```
class ImageFactory(factory.Factory):
    # The model expects "attributes"
    form_attributes = ['thumbnail', 'black-and-white']

class Meta:
    model = Image
    rename = {'form_attributes': 'attributes'}
```

strategy

Use this attribute to change the strategy used by a Factory. The default is CREATE_STRATEGY.

Attributes and methods

class factory.Factory

Class-level attributes:

Meta

_meta

New in version 2.4.0.

The FactoryOptions instance attached to a Factory class is available as a _meta attribute.

Params

New in version 2.7.0.

The extra parameters attached to a Factory are declared through a Params class. See the "Parameters" section for more information.

_options_class

New in version 2.4.0.

If a Factory subclass needs to define additional, extra options, it has to provide a custom FactoryOptions subclass.

A pointer to that custom class should be provided as _options_class so that the Factory-building metaclass can use it instead.

Base functions:

The Factory class provides a few methods for getting objects; the usual way being to simply call the class:

```
>>> UserFactory()  # Calls UserFactory.create()
>>> UserFactory(login='john')  # Calls UserFactory.create(login='john')
```

Under the hood, factory_boy will define the Factory __new__() method to call the default *strategy* of the Factory.

A specific strategy for getting instance can be selected by calling the adequate method:

classmethod build (cls, **kwargs)

Provides a new object, using the 'build' strategy.

classmethod build_batch (cls, size, **kwargs)

Provides a list of size instances from the Factory, through the 'build' strategy.

```
classmethod create (cls, **kwargs)
```

Provides a new object, using the 'create' strategy.

```
classmethod create_batch (cls, size, **kwargs)
```

Provides a list of size instances from the Factory, through the 'create' strategy.

classmethod stub (cls, **kwargs)

Provides a new stub

classmethod stub_batch (cls, size, **kwargs)

Provides a list of size stubs from the Factory.

classmethod generate(cls, strategy, **kwargs)

Provide a new instance, with the provided strategy.

classmethod generate_batch (cls, strategy, size, **kwargs)

Provides a list of size instances using the specified strategy.

classmethod simple_generate (cls, create, **kwargs)

Provide a new instance, either built (create=False) or created (create=True).

classmethod simple_generate_batch (cls, create, size, **kwargs)

Provides a list of size instances, either built or created according to create.

Extension points:

A Factory subclass may override a couple of class methods to adapt its behaviour:

classmethod _adjust_kwargs (cls, **kwargs)

The _adjust_kwargs() extension point allows for late fields tuning.

It is called once keyword arguments have been resolved and post-generation items removed, but before the *inline_args* extraction phase.

```
class UserFactory(factory.Factory):

    @classmethod
    def _adjust_kwargs(cls, **kwargs):
        # Ensure ``lastname`` is upper-case.
        kwargs['lastname'] = kwargs['lastname'].upper()
        return kwargs
```

classmethod _setup_next_sequence (cls)

This method will compute the first value to use for the sequence counter of this factory.

It is called when the first instance of the factory (or one of its subclasses) is created.

Subclasses may fetch the next free ID from the database, for instance.

classmethod _build (cls, model_class, *args, **kwargs)

This class method is called whenever a new instance needs to be built. It receives the model class (provided to model), and the positional and keyword arguments to use for the class once all has been computed.

Subclasses may override this for custom APIs.

classmethod _create (cls, model_class, *args, **kwargs)

The _create() method is called whenever an instance needs to be created. It receives the same arguments as _build().

Subclasses may override this for specific persistence backends:

```
class BaseBackendFactory(factory.Factory):
    class Meta:
        abstract = True # Optional

def _create(cls, model_class, *args, **kwargs):
        obj = model_class(*args, **kwargs)
```

```
obj.save()
return obj
```

classmethod _after_postgeneration (cls, obj, create, results=None)

Parameters

- **obj** (object) The object just generated
- create (bool) Whether the object was 'built' or 'created'
- results (dict) Map of post-generation declaration name to call result

The _after_postgeneration() is called once post-generation declarations have been handled.

Its arguments allow to handle specifically some post-generation return values, for instance.

Advanced functions:

classmethod reset_sequence (cls, value=None, force=False)

Parameters

- **value** (*int*) The value to reset the sequence to
- force (bool) Whether to force-reset the sequence

Allows to reset the sequence counter for a Factory. The new value can be passed in as the value argument:

```
>>> SomeFactory.reset_sequence(4)
>>> SomeFactory._next_sequence
4
```

Since subclasses of a non-abstract Factory share the same sequence counter, special care needs to be taken when resetting the counter of such a subclass.

By default, reset_sequence() will raise a ValueError when called on a subclassed Factory subclass. This can be avoided by passing in the force=True flag:

```
>>> InheritedFactory.reset_sequence()
Traceback (most recent call last):
    File "factory_boy/tests/test_base.py", line 179, in test_reset_sequence_subclass_parent
        SubTestObjectFactory.reset_sequence()
    File "factory_boy/factory/base.py", line 250, in reset_sequence
        "Cannot reset the sequence of a factory subclass. "
ValueError: Cannot reset the sequence of a factory subclass. Please call reset_sequence() or
>>> InheritedFactory.reset_sequence(force=True)
```

This is equivalent to calling reset_sequence() on the base factory in the chain.

Parameters

New in version 2.7.0.

Some models have many fields that can be summarized by a few parameters; for instance, a train with many cars — each complete with serial number, manufacturer, ...; or an order that can be pending/shipped/received, with a few fields to describe each step.

When building instances of such models, a couple of parameters can be enough to determine all other fields; this is handled by the *Params* section of a *Factory* declaration.

Simple parameters

Some factories only need little data:

```
class ConferenceFactory(factory.Factory):
    class Meta:
        model = Conference

class Params:
        duration = 'short' # Or 'long'

start_date = factory.fuzzy.FuzzyDate()
    end_date = factory.LazyAttribute(
        lambda o: o.start_date + datetime.timedelta(days=2 if o.duration == 'short' else 7)
)
sprints_start = factory.LazyAttribute(
        lambda o: o.end_date - datetime.timedelta(days=0 if o.duration == 'short' else 1)
)
```

```
>>> Conference(duration='short')
<Conference: DUTH 2015 (2015-11-05 - 2015-11-08, sprints 2015-11-08)>
>>> Conference(duration='long')
<Conference: DjangoConEU 2016 (2016-03-30 - 2016-04-03, sprints 2016-04-02)>
```

Any simple parameter provided to the Factory. Params section is available to the whole factory, but not passed to the final class (similar to the exclude behavior).

Traits

```
class factory.Trait (**kwargs)
    New in version 2.7.0.
```

A trait's parameters are the fields it should alter when enabled.

For more complex situations, it is helpful to override a few fields at once:

Such a *Trait* is activated or disabled by a single boolean field:

```
>>> OrderFactory()
<Order: pending>
Order(state='pending')
>>> OrderFactory(shipped=True)
<Order: shipped by John Doe on 2016-04-02>
```

A Trait can be enabled/disabled by a Factory subclass:

```
class ShippedOrderFactory(OrderFactory):
    shipped = True
```

Values set in a *Trait* can be overridden by call-time values:

```
>>> OrderFactory(shipped=True, shipped_on=last_year)
<Order: shipped by John Doe on 2015-04-20>
```

Traits can be chained:

```
class OrderFactory(factory.Factory):
   class Meta:
       model = Order
   # Can be pending/shipping/received
   state = 'pending'
   shipped on = None
   shipped_by = None
   received_on = None
   received_by = None
   class Params:
       shipped = factory.Trait(
           state='shipped',
            shipped_on=datetime.date.today,
            shipped_by=factory.SubFactory(EmployeeFactory),
       received = factory.Trait(
           shipped=True,
           state='received',
           shipped_on=datetime.date.today - datetime.timedelta(days=4),
           received_on=datetime.date.today,
           received_by=factory.SubFactory(CustomerFactory),
       )
```

```
>>> OrderFactory(received=True)
<Order: shipped by John Doe on 2016-03-20, received by Joan Smith on 2016-04-02>
```

A Trait might be overridden in Factory subclasses:

```
>>> LocalOrderFactory(received=True)
<Order: shipped by John Doe on 2016-04-01, received by Joan Smith on 2016-04-02>
```

Note: When overriding a *Trait*, the whole declaration **MUST** be replaced.

Strategies

factory_boy supports two main strategies for generating instances, plus stubs.

factory.BUILD_STRATEGY

The 'build' strategy is used when an instance should be created, but not persisted to any datastore.

It is usually a simple call to the __init__() method of the model class.

factory. CREATE STRATEGY

The 'create' strategy builds and saves an instance into its appropriate datastore.

This is the default strategy of factory_boy; it would typically instantiate an object, then save it:

```
>>> obj = self._associated_class(*args, **kwargs)
>>> obj.save()
>>> return obj
```

Warning: For backward compatibility reasons, the default behaviour of factory_boy is to call MyClass.objects.create(*args, **kwargs) when using the create strategy.

That policy will be used if the associated class has an objects attribute and the _create() classmethod of the Factory wasn't overridden.

```
factory.use_strategy(strategy)
```

Decorator

Change the default strategy of the decorated *Factory* to the chosen strategy:

```
@use_strategy(factory.BUILD_STRATEGY)
class UserBuildingFactory(UserFactory):
    pass
```

factory.STUB_STRATEGY

The 'stub' strategy is an exception in the factory_boy world: it doesn't return an instance of the model class, and actually doesn't require one to be present.

Instead, it returns an instance of StubObject whose attributes have been set according to the declarations.

```
class factory.StubObject(object)
```

A plain, stupid object. No method, no helpers, simply a bunch of attributes.

It is typically instantiated, then has its attributes set:

```
>>> obj = StubObject()
>>> obj.x = 1
>>> obj.y = 2
```

class factory.StubFactory(Factory)

An abstract Factory, with a default strategy set to STUB_STRATEGY.

factory.debug(logger='factory', stream=None)

Parameters

- logger (str) The name of the logger to enable debug for
- stream (file) The stream to send debug output to, defaults to sys.stderr

Context manager to help debugging factory_boy behavior. It will temporarily put the target logger (e.g 'factory') in debug mode, sending all output to :obj'~sys.stderr'; upon leaving the context, the logging levels are reset.

A typical use case is to understand what happens during a single factory call:

```
with factory.debug():
    obj = TestModel2Factory()
```

This will yield messages similar to those (artificial indentation):

```
BaseFactory: Preparing tests.test_using.TestModel2Factory(extra={})

LazyStub: Computing values for tests.test_using.TestModel2Factory(two=<OrderedDeclarationWrapp SubFactory: Instantiating tests.test_using.TestModelFactory(__containers=(<LazyStub for test BaseFactory: Preparing tests.test_using.TestModelFactory(extra={'__containers': (<LazyStub for test LazyStub: Computing values for tests.test_using.TestModelFactory(one=4)

LazyStub: Computed values, got tests.test_using.TestModelFactory(one=4)

BaseFactory: Generating tests.test_using.TestModel2Factory(two=<tests.test_using.TestModel objects

BaseFactory: Generating tests.test_using.TestModel2Factory(two=<tests.test_using.TestModel objects
```

5.2.2 Declarations

Faker

```
class factory.Faker (provider, locale=None, **kwargs)
```

In order to easily define realistic-looking factories, use the Faker attribute declaration.

This is a wrapper around fake-factory; its argument is the name of a fake-factory provider:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

name = factory.Faker('name')
```

```
>>> user = UserFactory()
>>> user.name
'Lucy Cechtelar'
```

locale

If a custom locale is required for one specific field, use the locale parameter:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

name = factory.Faker('name', locale='fr_FR')
```

```
>>> user = UserFactory()
>>> user.name
'Jean Valjean'
```

classmethod override_default_locale (cls, locale)

If the locale needs to be overridden for a whole test, use override default locale():

```
>>> with factory.Faker.override_default_locale('de_DE'):
... UserFactory()
<User: Johannes Brahms>
```

classmethod add_provider(cls, locale=None)

Some projects may need to fake fields beyond those provided by fake-factory; in such cases, use factory.Faker.add_provider() to declare additional providers for those fields:

```
factory.Faker.add_provider(SmileyProvider)

class FaceFactory(factory.Factory):
    class Meta:
        model = Face

smiley = factory.Faker('smiley')
```

LazyFunction

class factory.LazyFunction (method_to_call)

The LazyFunction is the simplest case where the value of an attribute does not depend on the object being built.

It takes as argument a method to call (function, lambda...); that method should not take any argument, though keyword arguments are safe but unused, and return a value.

```
class LogFactory(factory.Factory):
    class Meta:
        model = models.Log

    timestamp = factory.LazyFunction(datetime.now)
```

```
>>> LogFactory()
<Log: log at 2016-02-12 17:02:34>
>>> # The LazyFunction can be overriden
>>> LogFactory(timestamp=now - timedelta(days=1))
<Log: log at 2016-02-11 17:02:34>
```

Decorator

The class LazyFunction does not provide a decorator.

For complex cases, use LazyAttribute.lazy_attribute() directly.

LazyAttribute

```
class factory.LazyAttribute (method_to_call)
```

The LazyAttribute is a simple yet extremely powerful building brick for extending a Factory.

It takes as argument a method to call (usually a lambda); that method should accept the object being built as sole argument, and return a value.

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

username = 'john'
    email = factory.LazyAttribute(lambda o: '%s@example.com' % o.username)
```

```
>>> u = UserFactory()
>>> u.email
'john@example.com'
```

```
>>> u = UserFactory(username='leo')
>>> u.email
'leo@example.com'
```

The object passed to LazyAttribute is not an instance of the target class, but instead a LazyStub: a temporary container that computes the value of all declared fields.

Decorator

```
factory.lazy_attribute()
```

If a simple lambda isn't enough, you may use the <code>lazy_attribute()</code> decorator instead.

This decorates an instance method that should take a single argument, self; the name of the method will be used as the name of the attribute to fill with the return value of the method:

```
>>> joel = UserFactory(name=u"Joël")
>>> joel.email
u'joel@example.com'
```

Sequence

class factory.Sequence (lambda, type=int)

If a field should be unique, and thus different for all built instances, use a Sequence.

This declaration takes a single argument, a function accepting a single parameter - the current sequence counter - and returning the related value.

Note: An extra kwarg argument, type, may be provided. This feature was deprecated in 1.3.0 and will be removed in 2.0.0.

```
class UserFactory(factory.Factory)
  class Meta:
    model = User

phone = factory.Sequence(lambda n: '123-555-%04d' % n)
```

```
>>> UserFactory().phone
'123-555-0001'
```

```
>>> UserFactory().phone
'123-555-0002'
```

Decorator

```
factory.sequence()
```

As with <code>lazy_attribute()</code>, a decorator is available for complex situations.

sequence () decorates an instance method, whose self method will actually be the sequence counter - this might be confusing:

```
class UserFactory(factory.Factory)
    class Meta:
        model = User

@factory.sequence
    def phone(n):
        a = n // 10000
        b = n % 10000
        return '%03d-555-%04d' % (a, b)
```

```
>>> UserFactory().phone
'000-555-9999'
>>> UserFactory().phone
'001-555-0000'
```

Sharing

The sequence counter is shared across all Sequence attributes of the Factory:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

phone = factory.Sequence(lambda n: '%04d' % n)
    office = factory.Sequence(lambda n: 'A23-B%03d' % n)
```

```
>>> u = UserFactory()
>>> u.phone, u.office
'0041', 'A23-B041'
>>> u2 = UserFactory()
>>> u2.phone, u2.office
'0042', 'A23-B042'
```

Inheritance

When a Factory inherits from another Factory and the model of the subclass inherits from the model of the parent, the sequence counter is shared across the Factory classes:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

phone = factory.Sequence(lambda n: '123-555-%04d' % n)
```

```
class EmployeeFactory(UserFactory):
    office_phone = factory.Sequence(lambda n: '%04d' % n)
```

```
>>> u = UserFactory()
>>> u.phone
'123-555-0001'

>>> e = EmployeeFactory()
>>> e.phone, e.office_phone
'123-555-0002', '0002'

>>> u2 = UserFactory()
>>> u2.phone
'123-555-0003'
```

Forcing a sequence counter

If a specific value of the sequence counter is required for one instance, the __sequence keyword argument should be passed to the factory method.

This will force the sequence counter during the call, without altering the class-level value.

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

uid = factory.Sequence(int)
```

```
>>> UserFactory()
<User: 0>
>>> UserFactory()
<User: 1>
>>> UserFactory(__sequence=42)
<User: 42>
```

Warning: The impact of setting __sequence=n on a _batch call is undefined. Each generated instance may share a same counter, or use incremental values starting from the forced value.

LazyAttributeSequence

class factory.LazyAttributeSequence (method_to_call)

The LazyAttributeSequence declaration merges features of Sequence and LazyAttribute.

It takes a single argument, a function whose two parameters are, in order:

- The object being built
- The sequence counter

```
class UserFactory(factory.Factory):
    class Meta:
        model = User
```

```
login = 'john'
email = factory.LazyAttributeSequence(lambda o, n: '%s@s%d.example.com' % (o.login, n))
```

```
>>> UserFactory().email
'john@s1.example.com'
>>> UserFactory(login='jack').email
'jack@s2.example.com'
```

Decorator

factory.lazy_attribute_sequence (method_to_call)

As for <code>lazy_attribute()</code> and <code>sequence()</code>, the <code>lazy_attribute_sequence()</code> handles more complex cases:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

login = 'john'

@lazy_attribute_sequence
def email(self, n):
        bucket = n % 10
        return '%s@s%d.example.com' % (self.login, bucket)
```

SubFactory

```
class factory.SubFactory (factory, **kwargs)
```

This attribute declaration calls another *Factory* subclass, selecting the same build strategy and collecting extra kwargs in the process.

The SubFactory attribute should be called with:

- A Factory subclass as first argument, or the fully qualified import path to that Factory (see Circular imports)
- An optional set of keyword arguments that should be passed when calling that factory

Note: When passing an actual *Factory* for the factory argument, make sure to pass the class and not instance (i.e no () after the class):

```
class FooFactory(factory.Factory):
    class Meta:
        model = Foo

bar = factory.SubFactory(BarFactory) # Not BarFactory()
```

Definition

```
# A standard factory
class UserFactory(factory.Factory):
    class Meta:
        model = User

# Various fields
    first_name = 'John'
    last_name = factory.Sequence(lambda n: 'D%se' % ('o' * n)) # De, Doe, Dooe, Dooe,
    email = factory.LazyAttribute(lambda o: '%s.%s@example.org' % (o.first_name.lower()),

# A factory for an object with a 'User' field
class CompanyFactory(factory.Factory):
    class Meta:
        model = Company

name = factory.Sequence(lambda n: 'FactoryBoyz' + 'z' * n)

# Let's use our UserFactory to create that user, and override its first name.
owner = factory.SubFactory(UserFactory, first_name='Jack')
```

Calling

The wrapping factory will call of the inner factory:

```
>>> c = CompanyFactory()
>>> c
<Company: FactoryBoyz>

# Notice that the first_name was overridden
>>> c.owner
<User: Jack De>
>>> c.owner.email
jack.de@example.org
```

Fields of the SubFactory may be overridden from the external factory:

```
>>> c = CompanyFactory(owner__first_name='Henry')
>>> c.owner
<User: Henry Doe>

# Notice that the updated first_name was propagated to the email LazyAttribute.
>>> c.owner.email
henry.doe@example.org

# It is also possible to override other fields of the SubFactory
>>> c = CompanyFactory(owner__last_name='Jones')
>>> c.owner
<User: Henry Jones>
>>> c.owner.email
henry.jones@example.org
```

Strategies

The strategy chosen for the external factory will be propagated to all subfactories:

```
>>> c = CompanyFactory()
>>> c.pk  # Saved to the database
3
>>> c.owner.pk  # Saved to the database
8

>>> c = CompanyFactory.build()
>>> c.pk  # Not saved
None
>>> c.owner.pk  # Not saved either
None
```

Circular imports

Some factories may rely on each other in a circular manner. This issue can be handled by passing the absolute import path to the target *Factory* to the *SubFactory*.

New in version 1.3.0.

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

    username = 'john'
    main_group = factory.SubFactory('users.factories.GroupFactory')

class GroupFactory(factory.Factory):
    class Meta:
        model = Group

    name = "MyGroup"
    owner = factory.SubFactory(UserFactory)
```

Obviously, such circular relationships require careful handling of loops:

```
>>> owner = UserFactory(main_group=None)
>>> UserFactory(main_group__owner=owner)
<john (group: MyGroup)>
```

SelfAttribute

```
class factory.SelfAttribute(dotted_path_to_attribute)
```

Some fields should reference another field of the object being constructed, or an attribute thereof.

This is performed by the SelfAttribute declaration. That declaration takes a single argument, a dot-delimited path to the attribute to fetch:

```
class UserFactory(factory.Factory)
    class Meta:
        model = User

birthdate = factory.Sequence(lambda n: datetime.date(2000, 1, 1) + datetime.timedelta(days=n))
    birthmonth = factory.SelfAttribute('birthdate.month')
```

5.2. Reference 33

```
>>> u = UserFactory()
>>> u.birthdate
date(2000, 3, 15)
>>> u.birthmonth
3
```

Parents

When used in conjunction with SubFactory, the SelfAttribute gains an "upward" semantic through the double-dot notation, as used in Python imports.

factory.SelfAttribute('..country.language') means "Select the language of the country of the Factory calling me".

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

    language = 'en'

class CompanyFactory(factory.Factory):
    class Meta:
        model = Company

    country = factory.SubFactory(CountryFactory)
    owner = factory.SubFactory(UserFactory, language=factory.SelfAttribute('..country.language'))
```

```
>>> company = CompanyFactory()
>>> company.country.language
'fr'
>>> company.owner.language
'fr'
```

Obviously, this "follow parents" ability also handles overriding some attributes on call:

```
>>> company = CompanyFactory(country=china)
>>> company.owner.language
'cn'
```

This feature is also available to LazyAttribute and LazyAttributeSequence, through the factory_parent attribute of the passed-in object:

Iterator

class factory.Iterator(iterable, cycle=True, getter=None)

The *Iterator* declaration takes succesive values from the given iterable. When it is exhausted, it starts again from zero (unless cycle=False).

cycle

The cycle argument is only useful for advanced cases, where the provided iterable has no end (as wishing to cycle it means storing values in memory...).

New in version 1.3.0: The cycle argument is available as of v1.3.0; previous versions had a behaviour equivalent to cycle=False.

getter

A custom function called on each value returned by the iterable. See the *Getter* section for details.

New in version 1.3.0.

reset()

Reset the internal iterator used by the attribute, so that the next value will be the first value generated by the iterator.

May be called several times.

Each call to the factory will receive the next value from the iterable:

```
class UserFactory(factory.Factory)
lang = factory.Iterator(['en', 'fr', 'es', 'it', 'de'])
```

```
>>> UserFactory().lang
'en'
>>> UserFactory().lang
'fr'
```

When a value is passed in for the argument, the iterator will *not* be advanced:

```
>>> UserFactory().lang
'en'
>>> UserFactory(lang='cn').lang
'cn'
>>> UserFactory().lang
'fr'
```

Getter

Some situations may reuse an existing iterable, using only some component. This is handled by the *getter* attribute: this is a function that accepts as sole parameter a value from the iterable, and returns an adequate value.

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

# CATEGORY_CHOICES is a list of (key, title) tuples
    category = factory.Iterator(User.CATEGORY_CHOICES, getter=lambda c: c[0])
```

Decorator

```
factory.iterator(func)
```

When generating items of the iterator gets too complex for a simple list comprehension, use the *iterator()* decorator:

Warning: The decorated function takes no argument, notably no self parameter.

5.2. Reference 35

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

@factory.iterator
    def name():
        with open('test/data/names.dat', 'r') as f:
        for line in f:
            yield line
```

Resetting

In order to start back at the first value in an *Iterator*, simply call the *reset()* method of that attribute (accessing it from the bare *Factory* subclass):

```
>>> UserFactory().lang
'en'
>>> UserFactory().lang
'fr'
>>> UserFactory.lang.reset()
>>> UserFactory().lang
'en'
```

Dict and List

When a factory expects lists or dicts as arguments, such values can be generated through the whole range of factory_boy declarations, with the <code>Dict</code> and <code>List</code> attributes:

```
class factory.Dict(params|, dict_factory=factory.DictFactory|)
```

The Dict class is used for dict-like attributes. It receives as non-keyword argument a dictionary of fields to define, whose value may be any factory-enabled declarations:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

is_superuser = False
    roles = factory.Dict({
        'role1': True,
        'role2': False,
        'role3': factory.Iterator([True, False]),
        'admin': factory.SelfAttribute('..is_superuser'),
})
```

Note: Declarations used as a *Dict* values are evaluated within that *Dict*'s context; this means that you must use the ..foo syntax to access fields defined at the factory level.

On the other hand, the Sequence counter is aligned on the containing factory's one.

The Dict behaviour can be tuned through the following parameters:

dict_factory

The actual factory to use for generating the dict can be set as a keyword argument, if an exotic dictionary-like object (SortedDict, ...) is required.

```
class factory.List (items[, list_factory=factory.ListFactory])
The List can be used for list-like attributes.
```

Internally, the fields are converted into a index=value dict, which makes it possible to override some values at use time:

```
>>> u = UserFactory(flags__2='superadmin')
>>> u.flags
['user', 'active', 'superadmin']
```

The List behaviour can be tuned through the following parameters:

list_factory

The actual factory to use for generating the list can be set as a keyword argument, if another type (tuple, set, ...) is required.

Post-generation hooks

Some objects expect additional method calls or complex processing for proper definition. For instance, a User may need to have a related Profile, where the Profile is built from the User object.

To support this pattern, factory_boy provides the following tools:

- PostGenerationMethodCall: allows you to hook a particular attribute to a function call
- PostGeneration: this class allows calling a given function with the generated object as argument
- post_generation(): decorator performing the same functions as PostGeneration
- RelatedFactory: this builds or creates a given factory after building/creating the first Factory.

Post-generation hooks are called in the same order they are declared in the factory class, so that functions can rely on the side effects applied by the previous post-generation hook.

Extracting parameters

All post-building hooks share a common base for picking parameters from the set of attributes passed to the Factory.

For instance, a *PostGeneration* hook is declared as post:

```
class SomeFactory(factory.Factory):
    class Meta:
        model = SomeObject

    @post_generation
    def post(obj, create, extracted, **kwargs):
        obj.set_origin(create)
```

When calling the factory, some arguments will be extracted for this method:

5.2. Reference 37

- If a post argument is passed, it will be passed as the extracted field
- Any argument starting with post__XYZ will be extracted, its post__ prefix removed, and added to the kwargs passed to the post-generation hook.

Extracted arguments won't be passed to the model class.

Thus, in the following call:

```
>>> SomeFactory(
    post=1,
    post_x=2,
    post_y=3,
    post_z_t=42,
)
```

The post hook will receive 1 as extracted and {'y': 3, 'z_t': 42} as keyword arguments; {'post_x': 2} will be passed to SomeFactory._meta.model.

RelatedFactory

class factory.RelatedFactory (factory, factory_related_name='', **kwargs)

A RelatedFactory behaves mostly like a SubFactory, with the main difference that the related Factory will be generated after the base Factory.

factory

As for SubFactory, the factory argument can be:

- •A Factory subclass
- •Or the fully qualified path to a Factory subclass (see Circular imports for details)

name

The generated object (where the RelatedFactory attribute will set) may be passed to the related factory if the factory_related_name parameter is set.

It will be passed as a keyword argument, using the name value as keyword:

Note: When passing an actual *Factory* for the *factory* argument, make sure to pass the class and not instance (i.e no () after the class):

```
class FooFactory(factory.Factory):
    class Meta:
        model = Foo

bar = factory.RelatedFactory(BarFactory) # Not BarFactory()
```

```
class CityFactory(factory.Factory):
    class Meta:
        model = City

    capital_of = None
    name = "Toronto"

class CountryFactory(factory.Factory):
    class Meta:
        model = Country
```

```
lang = 'fr'
capital_city = factory.RelatedFactory(CityFactory, 'capital_of', name="Paris")
```

```
>>> france = CountryFactory()
>>> City.objects.get(capital_of=france)
<City: Paris>
```

Extra kwargs may be passed to the related factory, through the usual ATTR__SUBATTR syntax:

```
>>> england = CountryFactory(lang='en', capital_city__name="London")
>>> City.objects.get(capital_of=england)
<City: London>
```

If a value if passed for the RelatedFactory attribute, this disables RelatedFactory generation:

```
>>> france = CountryFactory()
>>> paris = City.objects.get()
>>> paris
<City: Paris>
>>> reunion = CountryFactory(capital_city=paris)
>>> City.objects.count() # No new capital_city generated
1
>>> guyane = CountryFactory(capital_city=paris, capital_city_name='Kourou')
>>> City.objects.count() # No new capital_city generated, ``name`` ignored.
1
```

Note: The target of the *RelatedFactory* is evaluated *after* the initial factory has been instantiated. This means that calls to *factory*. *SelfAttribute* cannot go higher than this *RelatedFactory*:

```
class CountryFactory(factory.Factory):
    class Meta:
        model = Country

lang = 'fr'
    capital_city = factory.RelatedFactory(CityFactory, 'capital_of',
        # factory.SelfAttribute('..lang') will crash, since the context of
        # ``CountryFactory`` has already been evaluated.
        main_lang=factory.SelfAttribute('capital_of.lang'),
)
```

PostGeneration

class factory.PostGeneration(callable)

The PostGeneration declaration performs actions once the model object has been generated.

Its sole argument is a callable, that will be called once the base object has been generated.

Once the base object has been generated, the provided callable will be called as callable (obj, create, extracted, **kwargs), where:

- obj is the base object previously generated
- create is a boolean indicating which strategy was used
- extracted is None unless a value was passed in for the PostGeneration declaration at Factory declaration time

5.2. Reference 39

• kwargs are any extra parameters passed as attr__key=value when calling the Factory:

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

login = 'john'
    make_mbox = factory.PostGeneration(
        lambda obj, create, extracted, **kwargs: os.makedirs(obj.login))
```

Decorator

```
factory.post_generation()
```

A decorator is also provided, decorating a single method accepting the same obj, created, extracted and keyword arguments as <code>PostGeneration</code>.

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

login = 'john'

@factory.post_generation
    def mbox(self, create, extracted, **kwargs):
        if not create:
            return
        path = extracted or os.path.join('/tmp/mbox/', self.login)
        os.path.makedirs(path)
        return path
```

```
>>> UserFactory.build() # Nothing was created
>>> UserFactory.create() # Creates dir /tmp/mbox/john
>>> UserFactory.create(login='jack') # Creates dir /tmp/mbox/jack
>>> UserFactory.create(mbox='/tmp/alt') # Creates dir /tmp/alt
```

PostGenerationMethodCall

class factory.PostGenerationMethodCall (method_name, *args, **kwargs)

The <code>PostGenerationMethodCall</code> declaration will call a method on the generated object just after instantiation. This declaration class provides a friendly means of generating attributes of a factory instance during initialization. The declaration is created using the following arguments:

method name

The name of the method to call on the model object

args

The default set of unnamed arguments to pass to the method given in method_name

kwargs

The default set of keyword arguments to pass to the method given in method_name

Once the factory instance has been generated, the method specified in method_name will be called on the generated object with any arguments specified in the PostGenerationMethodCall declaration, by default.

For example, to set a default password on a generated User instance during instantiation, we could make a declaration for a password attribute like below:

When we instantiate a user from the UserFactory, the factory will create a password attribute by calling User.set_password('defaultpassword'). Thus, by default, our users will have a password set to 'defaultpassword'.

If the PostGenerationMethodCall declaration contained no arguments or one argument, an overriding value can be passed directly to the method through a keyword argument matching the attribute name. For example we can override the default password specified in the declaration above by simply passing in the desired password as a keyword argument to the factory during instantiation.

```
>>> other_u = UserFactory(password='different') # Calls user.set_password('different')
>>> other_u.check_password('defaultpassword')
False
>>> other_u.check_password('different')
True
```

Note: For Django models, unless the object method called by <code>PostGenerationMethodCall</code> saves the object back to the database, we will have to explicitly remember to save the object back if we performed a <code>create()</code>.

```
>>> u = UserFactory.create() # u.password has not been saved back to the database
>>> u.save() # we must remember to do it ourselves
```

We can avoid this by subclassing from DjangoModelFactory, instead, e.g.,

If instead the PostGenerationMethodCall declaration uses two or more positional arguments, the overriding value must be an iterable. For example, if we declared the password attribute like the following,

```
class UserFactory(factory.Factory):
    class Meta:
        model = User

    username = 'user'
    password = factory.PostGenerationMethodCall('set_password', '', 'shal')
```

then we must be cautious to pass in an iterable for the password keyword argument when creating an instance from the factory:

5.2. Reference 41

Note: While this setup provides sane and intuitive defaults for most users, it prevents passing more than one argument when the declaration used zero or one.

In such cases, users are advised to either resort to the more powerful PostGeneration or to add the second expected argument default value to the PostGenerationMethodCall declaration (PostGenerationMethodCall('method', 'x', 'y_that_is_the_default'))

Keywords extracted from the factory arguments are merged into the defaults present in the <code>PostGenerationMethodCall</code> declaration.

```
>>> UserFactory(password__disabled=True)  # Calls user.set_password('', 'sha1', disabled=True)
```

5.2.3 Module-level functions

Beyond the Factory class and the various *Declarations* classes and methods, factory_boy exposes a few module-level functions, mostly useful for lightweight factory generation.

Lightweight factory declaration

```
factory.make_factory(klass, **kwargs)
```

The make_factory() function takes a class, declarations as keyword arguments, and generates a new Factory for that class accordingly:

An alternate base class to Factory can be specified in the FACTORY CLASS argument:

```
class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.User

login = 'john'
    email = factory.LazyAttribute(lambda u: '%s@example.com' % u.login)
```

New in version 2.0.0: The FACTORY_CLASS kwarg was added in 2.0.0.

Instance building

The factory module provides a bunch of shortcuts for creating a factory and extracting instances from them:

```
factory.build(klass, FACTORY_CLASS=None, **kwargs)
```

```
factory.build_batch (klass, size, FACTORY_CLASS=None, **kwargs)
```

Create a factory for klass using declarations passed in kwargs; return an instance built from that factory, or a list of size instances (for build_batch()).

Parameters

- klass (class) Class of the instance to build
- size (int) Number of instances to build
- **kwargs** Declarations to use for the generated factory
- **FACTORY CLASS** Alternate base class (instead of Factory)

factory.create(klass, FACTORY_CLASS=None, **kwargs)

```
factory.create_batch(klass, size, FACTORY_CLASS=None, **kwargs)
```

Create a factory for klass using declarations passed in kwargs; return an instance created from that factory, or a list of size instances (for <code>create_batch()</code>).

Parameters

- klass (class) Class of the instance to create
- size (int) Number of instances to create
- kwargs Declarations to use for the generated factory
- **FACTORY_CLASS** Alternate base class (instead of *Factory*)

factory.stub(klass, FACTORY_CLASS=None, **kwargs)

```
factory.stub_batch(klass, size, FACTORY_CLASS=None, **kwargs)
```

Create a factory for klass using declarations passed in kwargs; return an instance stubbed from that factory, or a list of size instances (for stub_batch()).

Parameters

- klass(class) Class of the instance to stub
- **size** (*int*) Number of instances to stub
- **kwargs** Declarations to use for the generated factory
- **FACTORY_CLASS** Alternate base class (instead of *Factory*)

factory.generate(klass, strategy, FACTORY_CLASS=None, **kwargs)

5.2. Reference 43

factory.generate batch (klass, strategy, size, FACTORY CLASS=None, **kwargs)

Create a factory for klass using declarations passed in kwargs; return an instance generated from that factory with the strategy strategy, or a list of size instances (for generate batch ()).

Parameters

- **klass** (*class*) Class of the instance to generate
- **strategy** (str) The strategy to use
- **size** (*int*) Number of instances to generate
- **kwargs** Declarations to use for the generated factory
- **FACTORY_CLASS** Alternate base class (instead of *Factory*)

factory.simple_generate(klass, create, FACTORY_CLASS=None, **kwargs)

factory.simple_generate_batch (klass, create, size, FACTORY_CLASS=None, **kwargs)

Create a factory for klass using declarations passed in kwargs; return an instance generated from that factory according to the <code>create</code> flag, or a list of <code>size</code> instances (for <code>simple_generate_batch()</code>).

Parameters

- **klass** (*class*) Class of the instance to generate
- create (bool) Whether to build (False) or create (True) instances
- **size** (*int*) Number of instances to generate
- **kwargs** Declarations to use for the generated factory
- **FACTORY_CLASS** Alternate base class (instead of *Factory*)

5.3 Using factory_boy with ORMs

factory_boy provides custom Factory subclasses for various ORMs, adding dedicated features.

5.3.1 Django

The first versions of factory_boy were designed specifically for Django, but the library has now evolved to be framework-independent.

Most features should thus feel quite familiar to Django users.

The DjangoModelFactory subclass

All factories for a Django Model should use the DjangoModelFactory base class.

class factory.django.DjangoModelFactory(factory.Factory)

Dedicated class for Django Model factories.

This class provides the following features:

- •The model attribute also supports the 'app.Model' syntax
- •create() uses Model.objects.create()
- •When using RelatedFactory or PostGeneration attributes, the base object will be saved once all post-generation hooks have run.

Note: With Django versions 1.8.0 to 1.8.3, it was no longer possible to call .build() on a factory if this factory used a *SubFactory* pointing to another model: Django refused to set a ForeignKey to an unsaved Model instance.

See https://code.djangoproject.com/ticket/10811 and https://code.djangoproject.com/ticket/25160 for details.

class factory.django.DjangoOptions (factory.base.FactoryOptions)

The class Meta on a DjangoModelFactory supports extra parameters:

database

New in version 2.5.0.

All queries to the related model will be routed to the given database. It defaults to 'default'.

django_get_or_create

New in version 2.4.0.

Fields whose name are passed in this list will be used to perform a Model.objects.get_or_create() instead of the usual Model.objects.create():

```
class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = 'myapp.User'  # Equivalent to ``model = myapp.models.User``
        django_get_or_create = ('username',)

username = 'john'
```

```
>>> User.objects.all()
[]
>>> UserFactory()
                                     # Creates a new user
<User: john>
>>> User.objects.all()
[<User: john>]
>>> UserFactory()
                                     # Fetches the existing user
<User: john>
>>> User.objects.all()
                                     # No new user!
[<User: john>]
>>> UserFactory(username='jack')
                                    # Creates another user
<User: jack>
>>> User.objects.all()
[<User: john>, <User: jack>]
```

Extra fields

```
class factory.django.FileField
```

Custom declarations for django.db.models.FileField

```
__init__ (self, from_path='', from_file='', data=b'', filename='example.dat')
```

Parameters

- from path (str) Use data from the file located at from path, and keep its filename
- **from_file** (*file*) Use the contents of the provided file object; use its filename if available, unless filename is also provided.
- from_func (func) Use function that returns a file object

- data (bytes) Use the provided bytes as file contents
- **filename** (str) The filename for the FileField

Note: If the value None was passed for the FileField field, this will disable field generation:

```
class MyFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.MyModel

    the_file = factory.django.FileField(filename='the_file.dat')
```

```
>>> MyFactory(the_file__data=b'uhuh').the_file.read()
b'uhuh'
>>> MyFactory(the_file=None).the_file
None
```

class factory.django.ImageField

Custom declarations for django.db.models.ImageField

```
__init__(self, from_path='', from_file='', filename='example.jpg', width=100, height=100, color='green', format='JPEG')
```

Parameters

- **from_path** (str) Use data from the file located at from_path, and keep its filename
- **from_file** (file) Use the contents of the provided file object; use its filename if available
- from_func (func) Use function that returns a file object
- **filename** (str) The filename for the ImageField
- width (int) The width of the generated image (default: 100)
- **height** (*int*) The height of the generated image (default: 100)
- **color** (*str*) The color of the generated image (default: 'green')
- **format** (str) The image format (as supported by PIL) (default: 'JPEG')

Note: If the value None was passed for the FileField field, this will disable field generation:

Note: Just as Django's django.db.models.ImageField requires the Python Imaging Library, this *ImageField* requires it too.

```
class MyFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.MyModel

    the_image = factory.django.ImageField(color='blue')
```

```
>>> MyFactory(the_image__width=42).the_image.width
42
>>> MyFactory(the_image=None).the_image
None
```

Disabling signals

Signals are often used to plug some custom code into external components code; for instance to create Profile objects on-the-fly when a new User object is saved.

This may interfere with finely tuned factories, which would create both using RelatedFactory.

To work around this problem, use the mute_signals() decorator/context manager:

```
factory.django.mute_signals(signal1,...)
```

Disable the list of selected signals when calling the factory, and reactivate them upon leaving.

```
# foo/factories.py
import factory
import factory.django

from . import models
from . import signals

@factory.django.mute_signals(signals.pre_save, signals.post_save)
class FooFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.Foo

# ...

def make_chain():
    with factory.django.mute_signals(signals.pre_save, signals.post_save):
    # pre_save/post_save won't be called here.
    return SomeFactory(), SomeOtherFactory()
```

5.3.2 Mogo

factory_boy supports Mogo-style models, through the MogoFactory class.

Mogo is a wrapper around the pymongo library for MongoDB.

```
class factory.mogo.MogoFactory (factory.Factory)
    Dedicated class for Mogo models.
```

This class provides the following features:

- •build() calls a model's new() method
- •create() builds an instance through new() then saves it.

5.3.3 MongoEngine

factory_boy supports MongoEngine-style models, through the MongoEngineFactory class.

mongoengine is a wrapper around the pymongo library for MongoDB.

```
class factory.mongoengine.MongoEngineFactory (factory.Factory)
```

Dedicated class for MongoEngine models.

This class provides the following features:

```
•build() calls a model's __init__ method
```

```
•create() builds an instance through __init__ then saves it.
```

Note: If the associated class <factory.FactoryOptions.model is a mongoengine.EmbeddedDocument, the create() function won't "save" it, since this wouldn't make sense.

This feature makes it possible to use *SubFactory* to create embedded document.

A minimalist example:

```
import mongoengine
class Address (mongoengine.EmbeddedDocument):
    street = mongoengine.StringField()
class Person(mongoengine.Document):
   name = mongoengine.StringField()
   address = mongoengine.EmbeddedDocumentField(Address)
import factory
class AddressFactory(factory.mongoengine.MongoEngineFactory):
   class Meta:
       model = Address
    street = factory.Sequence(lambda n: 'street%d' % n)
class PersonFactory(factory.mongoengine.MongoEngineFactory):
    class Meta:
       model = Person
   name = factory.Sequence(lambda n: 'name%d' % n)
   address = factory.SubFactory(AddressFactory)
```

5.3.4 SQLAlchemy

 $Factoy_boy\ also\ supports\ SQLAlchemy\ models\ through\ the\ \textit{SQLAlchemyModelFactory}\ class.$

To work, this class needs an SQLAlchemy session object affected to the Meta.sqlalchemy_session attribute.

```
{\bf class} \; {\tt factory.alchemy.SQLAlchemyModelFactory} \; (\textit{factory}. \textit{Factory}) \\
```

Dedicated class for SQLAlchemy models.

This class provides the following features:

```
•create() uses sqlalchemy.orm.session.Session.add()
```

```
class factory.alchemy.SQLAlchemyOptions (factory.base.FactoryOptions)
```

In addition to the usual parameters available in class Meta, a SQLAlchemyModelFactory also supports the following settings:

sqlalchemy_session

SQLAlchemy session to use to communicate with the database when creating an object through this SQLAlchemyModelFactory.

force_flush

Force a session flush() at the end of _create().

A (very) simple example:

```
from sqlalchemy import Column, Integer, Unicode, create_engine
from sqlalchemy.ext.declarative import declarative_base
from sqlalchemy.orm import scoped_session, sessionmaker
engine = create_engine('sqlite://')
session = scoped_session(sessionmaker(bind=engine))
Base = declarative_base()
class User (Base):
    """ A SQLAlchemy simple model class who represents a user """
   __tablename__ = 'UserTable'
   id = Column(Integer(), primary_key=True)
   name = Column(Unicode(20))
Base.metadata.create_all(engine)
import factory
class UserFactory(factory.alchemy.SQLAlchemyModelFactory):
   class Meta:
       model = User
       sqlalchemy_session = session # the SQLAlchemy session object
   id = factory.Sequence(lambda n: n)
   name = factory.Sequence(lambda n: u'User %d' % n)
```

```
>>> session.query(User).all()
[]
>>> UserFactory()
<User: User 1>
>>> session.query(User).all()
[<User: User 1>]
```

Managing sessions

Since SQLAlchemy is a general purpose library, there is no "global" session management system.

The most common pattern when working with unit tests and factory_boy is to use SQLAlchemy's sqlalchemy.orm.scoping.scoped_session:

- The test runner configures some project-wide scoped_session
- Each SQLAlchemyModelFactory subclass uses this scoped_session as its sqlalchemy_session
- The tearDown () method of tests calls Session.remove to reset the session.

Note: See the excellent SQLAlchemy guide on scoped_session for details of scoped_session's usage.

The basic idea is that declarative parts of the code (including factories) need a simple way to access the "current session", but that session will only be created and configured at a later point.

The scoped_session handles this, by virtue of only creating the session when a query is sent to the database.

Here is an example layout:

• A global (test-only?) file holds the scoped_session:

```
# myprojet/test/common.py

from sqlalchemy import orm
Session = orm.scoped_session(orm.sessionmaker())
```

• All factory access it:

```
# myproject/factories.py
import factory
import factory.alchemy

from . import models
from .test import common

class UserFactory(factory.alchemy.SQLAlchemyModelFactory):
    class Meta:
        model = models.User

    # Use the not-so-global scoped_session
    # Warning: DO NOT USE common.Session()!
    sqlalchemy_session = common.Session

name = factory.Sequence(lambda n: "User %d" % n)
```

• The test runner configures the scoped_session when it starts:

```
# myproject/test/runtests.py
import sqlalchemy
from . import common

def runtests():
    engine = sqlalchemy.create_engine('sqlite://')

# It's a scoped_session, and now is the time to configure it.
    common.Session.configure(bind=engine)
    run_the_tests
```

• test cases use this scoped_session, and clear it after each test (for isolation):

```
# myproject/test/test_stuff.py
import unittest
from . import common

class MyTest (unittest.TestCase):

    def setUp(self):
        # Prepare a new, clean session
        self.session = common.Session()

    def test_something(self):
        u = factories.UserFactory()
        self.assertEqual([u], self.session.query(User).all())
```

```
def tearDown(self):
    # Rollback the session => no changes to the database
    self.session.rollback()
    # Remove it, so that the next test gets a new Session()
    common.Session.remove()
```

5.4 Common recipes

Note: Most recipes below take on Django model examples, but can also be used on their own.

5.4.1 Dependent objects (ForeignKey)

When one attribute is actually a complex field (e.g a ForeignKey to another Model), use the SubFactory declaration:

```
# models.py
class User(models.Model):
    first_name = models.CharField()
    group = models.ForeignKey(Group)

# factories.py
import factory
from . import models

class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.User

first_name = factory.Sequence(lambda n: "Agent %03d" % n)
    group = factory.SubFactory(GroupFactory)
```

Choosing from a populated table

If the target of the ForeignKey should be chosen from a pre-populated table (e.g django.contrib.contenttypes.models.ContentType), simply use a factory.Iterator on the chosen queryset:

```
import factory, factory.django
from . import models

class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.User

language = factory.Iterator(models.Language.objects.all())
```

Here, models.Language.objects.all() won't be evaluated until the first call to UserFactory; thus avoiding DB queries at import time.

5.4.2 Reverse dependencies (reverse ForeignKey)

When a related object should be created upon object creation (e.g a reverse ForeignKey from another Model), use a RelatedFactory declaration:

```
# models.py
class User(models.Model):
    pass

class UserLog(models.Model):
        user = models.ForeignKey(User)
        action = models.CharField()

# factories.py
class UserFactory(factory.django.DjangoModelFactory):
        class Meta:
        model = models.User

log = factory.RelatedFactory(UserLogFactory, 'user', action=models.UserLog.ACTION_CREATE)
```

When a UserFactory is instantiated, factory_boy will call UserLogFactory(user=that_user, action=...) just before returning the created User.

Example: Django's Profile

Django (<1.5) provided a mechanism to attach a Profile to a User instance, using a OneToOneField from the Profile to the User.

A typical way to create those profiles was to hook a post-save signal to the User model.

factory_boy allows to define attributes of such profiles dynamically when creating a User:

```
class ProfileFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = my_models.Profile
   title = 'Dr'
    # We pass in profile=None to prevent UserFactory from creating another profile
    # (this disables the RelatedFactory)
   user = factory.SubFactory('app.factories.UserFactory', profile=None)
class UserFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = auth_models.User
   username = factory.Sequence(lambda n: "user_%d" % n)
    # We pass in 'user' to link the generated Profile to our just-generated User
    # This will call ProfileFactory(user=our_new_user), thus skipping the SubFactory.
   profile = factory.RelatedFactory(ProfileFactory, 'user')
   @classmethod
   def _generate(cls, create, attrs):
        """Override the default _generate() to disable the post-save signal."""
        # Note: If the signal was defined with a dispatch_uid, include that in both calls.
        post_save.disconnect(handler_create_user_profile, auth_models.User)
```

```
user = super(UserFactory, cls)._generate(create, attrs)
post_save.connect(handler_create_user_profile, auth_models.User)
return user
```

```
>>> u = UserFactory(profile__title=u"Lord")
>>> u.get_profile().title
u"Lord"
```

Such behaviour can be extended to other situations where a signal interferes with factory_boy related factories.

Note: When any RelatedFactory or post_generation attribute is defined on the DjangoModelFactory subclass, a second save () is performed after the call to _create().

Code working with signals should thus override the _generate() method.

5.4.3 Simple Many-to-many relationship

Building the adequate link between two models depends heavily on the use case; factory_boy doesn't provide a "all in one tools" as for SubFactory or RelatedFactory, users will have to craft their own depending on the model.

The base building block for this feature is the post_generation hook:

```
# models.py
class Group (models.Model):
   name = models.CharField()
class User (models.Model):
   name = models.CharField()
    groups = models.ManyToManyField(Group)
# factories.py
class GroupFactory(factory.django.DjangoModelFactory):
    class Meta:
       model = models.Group
   name = factory.Sequence(lambda n: "Group #%s" % n)
class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.User
   name = "John Doe"
   @factory.post_generation
    def groups(self, create, extracted, **kwargs):
        if not create:
            # Simple build, do nothing.
            return
        if extracted:
            # A list of groups were passed in, use them
            for group in extracted:
                self.groups.add(group)
```

When calling UserFactory () or UserFactory .build (), no group binding will be created.

But when UserFactory.create(groups=(group1, group2, group3)) is called, the groups declaration will add passed in groups to the set of groups for the user.

5.4.4 Many-to-many relation with a 'through'

If only one link is required, this can be simply performed with a RelatedFactory. If more links are needed, simply add more RelatedFactory declarations:

```
# models.py
class User(models.Model):
   name = models.CharField()
class Group (models.Model):
   name = models.CharField()
   members = models.ManyToManyField(User, through='GroupLevel')
class GroupLevel (models.Model):
   user = models.ForeignKey(User)
   group = models.ForeignKey(Group)
   rank = models.IntegerField()
# factories.pv
class UserFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = models.User
   name = "John Doe"
class GroupFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = models.Group
   name = "Admins"
class GroupLevelFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = models.GroupLevel
   user = factory.SubFactory(UserFactory)
   group = factory.SubFactory(GroupFactory)
   rank = 1
class UserWithGroupFactory (UserFactory):
   membership = factory.RelatedFactory(GroupLevelFactory, 'user')
class UserWith2GroupsFactory(UserFactory):
   membership1 = factory.RelatedFactory(GroupLevelFactory, 'user', group__name='Group1')
   membership2 = factory.RelatedFactory(GroupLevelFactory, 'user', group__name='Group2')
```

Whenever the UserWithGroupFactory is called, it will, as a post-generation hook, call the GroupLevelFactory, passing the generated user as a user field:

- 1. UserWithGroupFactory() generates a User instance, obj
- 2. It calls GroupLevelFactory (user=obj)
- 3. It returns obj

When using the UserWith2GroupsFactory, that behavior becomes:

```
1. UserWith2GroupsFactory() generates a User instance, obj
```

- 2. It calls GroupLevelFactory (user=obj, group__name='Group1')
- 3. It calls GroupLevelFactory (user=obj, group__name='Group2')
- 4. It returns ob i

5.4.5 Copying fields to a SubFactory

When a field of a related class should match one of the container:

```
# models.py
class Country(models.Model):
    name = models.CharField()
    lang = models.CharField()

class User(models.Model):
    name = models.CharField()
    lang = models.CharField()
    country = models.ForeignKey(Country)

class Company(models.Model):
    name = models.CharField()
    owner = models.ForeignKey(User)
    country = models.ForeignKey(Country)
```

Here, we want:

- The User to have the lang of its country (factory.SelfAttribute('country.lang'))
- The Company owner to live in the country of the company (factory. SelfAttribute ('..country'))

```
# factories.py
class CountryFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = models.Country
   name = factory.Iterator(["France", "Italy", "Spain"])
   lang = factory.Iterator(['fr', 'it', 'es'])
class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
       model = models.User
   name = "John"
   lang = factory.SelfAttribute('country.lang')
   country = factory.SubFactory(CountryFactory)
class CompanyFactory(factory.django.DjangoModelFactory):
   class Meta:
       model = models.Company
   name = "ACME, Inc."
   country = factory.SubFactory(CountryFactory)
   owner = factory.SubFactory(UserFactory, country=factory.SelfAttribute('..country'))
```

If the value of a field on the child factory is indirectly derived from a field on the parent factory, you will need to use LazyAttribute and poke the "factory_parent" attribute.

This time, we want the company owner to live in a country neighboring the country of the company:

```
class CompanyFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.Company

name = "ACME, Inc."
    country = factory.SubFactory(CountryFactory)
    owner = factory.SubFactory(UserFactory,
        country=factory.LazyAttribute(lambda o: get_random_neighbor(o.factory_parent.country)))
```

5.4.6 Custom manager methods

Sometimes you need a factory to call a specific manager method other then the default Model.objects.create() method:

```
class UserFactory(factory.DjangoModelFactory):
    class Meta:
        model = UserenaSignup

    username = "17d8s"
    email = "my_name@example.com"
    password = "my_password"

@classmethod
    def _create(cls, model_class, *args, **kwargs):
        """Override the default ``_create`` with our custom call."""
        manager = cls._get_manager(model_class)
        # The default would use ``manager.create(*args, **kwargs)``
        return manager.create_user(*args, **kwargs)
```

5.4.7 Forcing the sequence counter

A common pattern with factory_boy is to use a factory. Sequence declaration to provide varying values to attributes declared as unique.

However, it is sometimes useful to force a given value to the counter, for instance to ensure that tests are properly reproductible.

factory_boy provides a few hooks for this:

Forcing the value on a per-call basis In order to force the counter for a specific *Factory* instantiation, just pass the value in the __sequence=42 parameter:

```
class AccountFactory(factory.Factory):
    class Meta:
        model = Account
    uid = factory.Sequence(lambda n: n)
    name = "Test"
```

```
>>> obj1 = AccountFactory(name="John Doe", __sequence=10)
>>> obj1.uid # Taken from the __sequence counter
10
>>> obj2 = AccountFactory(name="Jane Doe")
```

```
>>> obj2.uid # The base sequence counter hasn't changed
1
```

Resetting the counter globally If all calls for a factory must start from a deterministic number, use factory.Factory.reset_sequence(); this will reset the counter to its initial value (as defined by factory.Factory._setup_next_sequence()).

```
>>> AccountFactory().uid
1
>>> AccountFactory().uid
2
>>> AccountFactory.reset_sequence()
>>> AccountFactory().uid # Reset to the initial value
1
>>> AccountFactory().uid
2
```

It is also possible to reset the counter to a specific value:

```
>>> AccountFactory.reset_sequence(10)
>>> AccountFactory().uid
10
>>> AccountFactory().uid
11
```

This recipe is most useful in a TestCase's setUp() method.

Forcing the initial value for all projects The sequence counter of a *Factory* can also be set automatically upon the first call through the _setup_next_sequence() method; this helps when the objects's attributes mustn't conflict with pre-existing data.

A typical example is to ensure that running a Python script twice will create non-conflicting objects, by setting up the counter to "max used value plus one":

```
class AccountFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.Account

@classmethod
def _setup_next_sequence(cls):
        try:
            return models.Accounts.objects.latest('uid').uid + 1
        except models.Account.DoesNotExist:
            return 1
```

```
>>> Account.objects.create(uid=42, name="Blah")
>>> AccountFactory.create() # Sets up the account number based on the latest uid
<Account uid=43, name=Test>
```

5.4.8 Converting a factory's output to a dict

In order to inject some data to, say, a REST API, it can be useful to fetch the factory's data as a dict.

Internally, a factory will:

- 1. Merge declarations and overrides from all sources (class definition, call parameters, ...)
- 2. Resolve them into a dict
- 3. Pass that dict as keyword arguments to the model's build/create function

In order to get a dict, we'll just have to swap the model; the easiest way is to use factory.build():

```
class UserFactory(factory.django.DjangoModelFactory):
    class Meta:
        model = models.User

first_name = factory.Sequence(lambda n: "Agent %03d" % n)
    username = factory.Faker('username')
```

```
>>> factory.build(dict, FACTORY_CLASS=UserFactory)
{'first_name': "Agent 001", 'username': 'john_doe'}
```

5.5 Fuzzy attributes

Note: Now that FactoryBoy includes the factory.Faker class, most of these built-in fuzzers are deprecated in favor of their Faker equivalents. Further discussion here: https://github.com/FactoryBoy/factory_boy/issues/271/

Some tests may be interested in testing with fuzzy, random values.

This is handled by the factory. fuzzy module, which provides a few random declarations.

Note: Use import factory.fuzzy to load this module.

5.5.1 FuzzyAttribute

class factory.fuzzy.FuzzyAttribute

The FuzzyAttribute uses an arbitrary callable as fuzzer. It is expected that successive calls of that function return various values.

fuzzer

The callable that generates random values

5.5.2 FuzzyText

class factory.fuzzyText (length=12, chars=string.ascii_letters, prefix='')

The FuzzyText fuzzer yields random strings beginning with the given prefix, followed by length charactes chosen from the chars character set, and ending with the given suffix.

length

int, the length of the random part

prefix

text, an optional prefix to prepend to the random part

suffix

text, an optional suffix to append to the random part

chars

char iterable, the chars to choose from; defaults to the list of ascii letters and numbers.

5.5.3 FuzzyChoice

```
class factory.fuzzy.FuzzyChoice(choices)
```

The FuzzyChoice fuzzer yields random choices from the given iterable.

Note: The passed in *choices* will be converted into a list upon first use, not at declaration time.

This allows passing in, for instance, a Django queryset that will only hit the database during the database, not at import time.

choices

The list of choices to select randomly

5.5.4 FuzzyInteger

```
class factory.fuzzy.FuzzyInteger(low[, high[, step]])
```

The FuzzyInteger fuzzer generates random integers within a given inclusive range.

The low bound may be omitted, in which case it defaults to 0:

```
>>> fi = FuzzyInteger(0, 42)
>>> fi.low, fi.high
0, 42

>>> fi = FuzzyInteger(42)
>>> fi.low, fi.high
0, 42
```

low

int, the inclusive lower bound of generated integers

high

int, the inclusive higher bound of generated integers

step

```
int, the step between values in the range; for instance, a FuzzyInteger(0, 42, step=3) might only yield values from [0, 3, 6, 9, 12, 15, 18, 21, 24, 27, 30, 33, 36, 39, 42].
```

5.5.5 FuzzyDecimal

```
class factory.fuzzy.FuzzyDecimal(low[, high[, precision=2]])
```

The FuzzyDecimal fuzzer generates random decimals within a given inclusive range.

The low bound may be omitted, in which case it defaults to 0:

```
>>> FuzzyDecimal(0.5, 42.7)
>>> fi.low, fi.high
0.5, 42.7

>>> fi = FuzzyDecimal(42.7)
>>> fi.low, fi.high
0.0, 42.7

>>> fi = FuzzyDecimal(0.5, 42.7, 3)
```

```
>>> fi.low, fi.high, fi.precision 0.5, 42.7, 3
```

low

decimal, the inclusive lower bound of generated decimals

high

decimal, the inclusive higher bound of generated decimals

precision

int, the number of digits to generate after the dot. The default is 2 digits.

5.5.6 FuzzyFloat

```
class factory.fuzzy.FuzzyFloat(low[, high])
```

The FuzzyFloat fuzzer provides random float objects within a given inclusive range.

```
>>> FuzzyFloat(0.5, 42.7)
>>> fi.low, fi.high
0.5, 42.7

>>> fi = FuzzyFloat(42.7)
>>> fi.low, fi.high
0.0, 42.7
```

low

decimal, the inclusive lower bound of generated floats

high

decimal, the inclusive higher bound of generated floats

5.5.7 FuzzyDate

```
class factory.fuzzy.FuzzyDate(start_date[, end_date])
```

The FuzzyDate fuzzer generates random dates within a given inclusive range.

The end_date bound may be omitted, in which case it defaults to the current date:

```
>>> fd = FuzzyDate(datetime.date(2008, 1, 1))
>>> fd.start_date, fd.end_date
datetime.date(2008, 1, 1), datetime.date(2013, 4, 16)
```

start_date

datetime.date, the inclusive lower bound of generated dates

end_date

datetime.date, the inclusive higher bound of generated dates

5.5.8 FuzzyDateTime

The FuzzyDateTime fuzzer generates random timezone-aware datetime within a given inclusive range.

The end_dt bound may be omitted, in which case it defaults to datetime.datetime.now() localized into the UTC timezone.

```
>>> fdt = FuzzyDateTime(datetime.datetime(2008, 1, 1, tzinfo=UTC))
>>> fdt.start_dt, fdt.end_dt
datetime.datetime(2008, 1, 1, tzinfo=UTC), datetime.datetime(2013, 4, 21, 19, 13, 32, 458487, tz
```

The force_XXX keyword arguments force the related value of generated datetimes:

```
>>> fdt = FuzzyDateTime(datetime.datetime(2008, 1, 1, tzinfo=UTC), datetime.datetime(2009, 1, 1,
... force_day=3, force_second=42)
>>> fdt.evaluate(2, None, False) # Actual code used by ``SomeFactory.build()``
datetime.datetime(2008, 5, 3, 12, 13, 42, 124848, tzinfo=UTC)
```

start_dt

datetime.datetime, the inclusive lower bound of generated datetimes

end dt

datetime.datetime, the inclusive upper bound of generated datetimes

force_year

int or None; if set, forces the year of generated datetime.

force month

int or None; if set, forces the month of generated datetime.

force_day

int or None; if set, forces the day of generated datetime.

force hour

int or None; if set, forces the hour of generated datetime.

force_minute

int or None; if set, forces the minute of generated datetime.

force_second

int or None; if set, forces the second of generated datetime.

force microsecond

int or None; if set, forces the microsecond of generated datetime.

5.5.9 FuzzyNaiveDateTime

```
class factory.fuzzy.FuzzyNaiveDateTime (start\_dt[, end\_dt[, force\_year=None, force\_month=None, force\_day=None, force\_hour=None, force\_minute=None, force\_second=None, force\_microsecond=None)
```

The FuzzyNaiveDateTime fuzzer generates random naive datetime within a given inclusive range.

The end_dt bound may be omitted, in which case it defaults to datetime.datetime.now():

```
>>> fdt = FuzzyNaiveDateTime(datetime.datetime(2008, 1, 1))
>>> fdt.start_dt, fdt.end_dt
datetime.datetime(2008, 1, 1), datetime.datetime(2013, 4, 21, 19, 13, 32, 458487)
```

The force XXX keyword arguments force the related value of generated datetimes:

```
>>> fdt = FuzzyNaiveDateTime(datetime.datetime(2008, 1, 1), datetime.datetime(2009, 1, 1),
... force_day=3, force_second=42)
>>> fdt.evaluate(2, None, False) # Actual code used by ``SomeFactory.build()``
datetime.datetime(2008, 5, 3, 12, 13, 42, 124848)
```

start dt

datetime.datetime, the inclusive lower bound of generated datetimes

end dt

datetime.datetime, the inclusive upper bound of generated datetimes

force_year

int or None; if set, forces the year of generated datetime.

force month

int or None; if set, forces the month of generated datetime.

force_day

int or None; if set, forces the day of generated datetime.

force_hour

int or None; if set, forces the hour of generated datetime.

force minute

int or None; if set, forces the minute of generated datetime.

force second

int or None; if set, forces the second of generated datetime.

force microsecond

int or None; if set, forces the microsecond of generated datetime.

5.5.10 Custom fuzzy fields

Alternate fuzzy fields may be defined. They should inherit from the BaseFuzzyAttribute class, and override its fuzz () method.

class factory.fuzzy.BaseFuzzyAttribute

Base class for all fuzzy attributes.

fuzz (self)

The method responsible for generating random values. *Must* be overridden in subclasses.

5.5.11 Managing randomness

Using random in factories allows to "fuzz" a program efficiently. However, it's sometimes required to *reproduce* a failing test.

factory. fuzzy uses a separate instance of random. Random, and provides a few helpers for this:

```
factory.fuzzy.get_random_state()
```

Call get_random_state() to retrieve the random generator's current state.

```
factory.fuzzy.set_random_state(state)
```

Use set_random_state() to set a custom state into the random generator (fetched from get_random_state() in a previous run, for instance)

```
factory.fuzzy.reseed_random(seed)
```

The reseed_random() function allows to load a chosen seed into the random generator.

Custom BaseFuzzyAttribute subclasses **SHOULD** use factory.fuzzy._random as a randomness source; this ensures that data they generate can be regenerated using the simple state from get_random_state().

5.6 Examples

Here are some real-world examples of using FactoryBoy.

5.6.1 Objects

First, let's define a couple of objects:

```
class Account (object):
    def __init__(self, username, email):
        self.username = username
        self.email = email
   def __str__(self):
        return '%s (%s)' % (self.username, self.email)
class Profile(object):
   GENDER_MALE = 'm'
   GENDER_FEMALE = 'f'
   GENDER_UNKNOWN = 'u' # If the user refused to give it
    def __init__(self, account, gender, firstname, lastname, planet='Earth'):
        self.account = account
        self.gender = gender
        self.firstname = firstname
        self.lastname = lastname
        self.planet = planet
    def __unicode__(self):
        return u'%s %s (%s)' % (
            unicode (self.firstname),
            unicode (self.lastname),
            unicode (self.account.accountname),
```

5.6.2 Factories

And now, we'll define the related factories:

```
import datetime
import factory
import random

from . import objects

class AccountFactory(factory.Factory):
    class Meta:
        model = objects.Account

    username = factory.Sequence(lambda n: 'john%s' % n)
    email = factory.LazyAttribute(lambda o: '%s@example.org' % o.username)
    date_joined = factory.LazyFunction(datetime.datetime.now)
```

5.6. Examples 63

```
class ProfileFactory(factory.Factory):
    class Meta:
        model = objects.Profile

    account = factory.SubFactory(AccountFactory)
    gender = factory.Iterator([objects.Profile.GENDER_MALE, objects.Profile.GENDER_FEMALE])
    firstname = u'John'
    lastname = u'Doe'
```

We have now defined basic factories for our Account and Profile classes.

If we commonly use a specific variant of our objects, we can refine a factory accordingly:

```
class FemaleProfileFactory(ProfileFactory):
    gender = objects.Profile.GENDER_FEMALE
    firstname = u'Jane'
    user_username = factory.Sequence(lambda n: 'jane%s' % n)
```

5.6.3 Using the factories

We can now use our factories, for tests:

```
import unittest
from . import business_logic
from . import factories
from . import objects
class MyTestCase(unittest.TestCase):
   def test_send_mail(self):
       account = factories.AccountFactory()
        email = business_logic.prepare_email(account, subject='Foo', text='Bar')
        self.assertEqual(email.to, account.email)
    def test_get_profile_stats(self):
       profiles = []
        profiles.extend(factories.ProfileFactory.create_batch(4))
        profiles.extend(factories.FemaleProfileFactory.create_batch(2))
        profiles.extend(factories.ProfileFactory.create_batch(2, planet="Tatooine"))
        stats = business_logic.profile_stats(profiles)
        self.assertEqual({'Earth': 6, 'Mars': 2}, stats.planets)
        self.assertLess(stats.genders[objects.Profile.GENDER_FEMALE], 2)
```

Or for fixtures:

```
from . import factories

def make_objects():
    factories.ProfileFactory.create_batch(size=50)

# Let's create a few, known objects.
```

```
factories.ProfileFactory(
    gender=objects.Profile.GENDER_MALE,
    firstname='Luke',
    lastname='Skywalker',
    planet='Tatooine',
)

factories.ProfileFactory(
    gender=objects.Profile.GENDER_FEMALE,
    firstname='Leia',
    lastname='Organa',
    planet='Alderaan',
)
```

5.7 Internals

5.8 ChangeLog

5.8.1 2.8.1 (2016-12-17)

Bugfix:

• Fix packaging issues.

5.8.2 2.8.0 (2016-12-17)

New:

- issue #240: Call post-generation declarations in the order they were declared, thanks to Oleg Pidsadnyi.
- issue #309: Provide new options for SQLAlchemy session persistence

Bugfix:

• issue #334: Adjust for the package change in faker

5.8.3 2.7.0 (2016-04-19)

New:

- issue #267: Add factory.LazyFunction to remove unneeded lambda parameters, thanks to Hervé Cauwelier.
- issue #251: Add parameterized factories and traits
- issue #256, issue #292: Improve error messages in corner cases

Removed:

• issue #278: Formally drop support for Python2.6

5.7. Internals 65

5.8.4 2.6.1 (2016-02-10)

New:

• issue #262: Allow optional forced flush on SQLAlchemy, courtesy of Minjung.

5.8.5 2.6.0 (2015-10-20)

New:

- Add factory. FactoryOptions. rename to help handle conflicting names (issue #206)
- Add support for random-yet-realistic values through fake-factory, through the factory. Faker class.
- factory. Iterator no longer begins iteration of its argument at import time, thus allowing to pass in a lazy iterator such as a Django queryset (i.e factory. Iterator (models.MyThingy.objects.all())).
- Simplify imports for ORM layers, now available through a simple factory import, at factory.alchemy.SQLAlchemyModelFactory / factory.django.DjangoModelFactory / factory.mongoengine.MongoEngineFactory.

Bugfix:

- issue #201: Properly handle custom Django managers when dealing with abstract Django models.
- issue #212: Fix factory.django.mute_signals() to handle Django's signal caching
- issue #228: Don't load django.apps.apps.get_model() until required
- issue #219: Stop using mogo.model.Model.new(), deprecated 4 years ago.

5.8.6 2.5.2 (2015-04-21)

Bugfix:

- Add support for Django 1.7/1.8
- Add support for mongoengine>=0.9.0 / pymongo>=2.1

5.8.7 2.5.1 (2015-03-27)

Bugfix:

- Respect custom managers in DjangoModelFactory (see issue #192)
- Allow passing declarations (e.g Sequence) as parameters to FileField and ImageField.

5.8.8 2.5.0 (2015-03-26)

New:

- Add support for getting/setting factory. fuzzy's random state (see issue #175, issue #185).
- Support lazy evaluation of iterables in factory.fuzzy.FuzzyChoice (see issue #184).
- Support non-default databases at the factory level (see issue #171)
- Make factory.django.FileField and factory.django.ImageField non-post_generation, i.e normal fields also available in save () (see issue #141).

Bugfix:

- Avoid issues when using factory.django.mute_signals() on a base factory class (see issue #183).
- Fix limitations of factory. StubFactory, that can now use factory. SubFactory and co (see issue #131).

Deprecation:

- Remove deprecated features from 2.4.0 (2014-06-21)
- Remove the auto-magical sequence setup (based on the latest primary key value in the database) for Django and SQLAlchemy; this relates to issues issue #170, issue #153, issue #111, issue #103, issue #92, issue #78. See https://github.com/FactoryBoy/factory_boy/commit/13d310f for technical details.

Warning: Version 2.5.0 removes the 'auto-magical sequence setup' bug-and-feature. This could trigger some bugs when tests expected a non-zero sequence reference.

Upgrading

Warning: Version 2.5.0 removes features that were marked as deprecated in v2.4.0.

All FACTORY_*-style attributes are now declared in a class Meta: section:

```
# Old-style, deprecated
class MyFactory(factory.Factory):
    FACTORY_FOR = models.MyModel
    FACTORY_HIDDEN_ARGS = ['a', 'b', 'c']

# New-style
class MyFactory(factory.Factory):
    class Meta:
        model = models.MyModel
        exclude = ['a', 'b', 'c']
```

A simple shell command to upgrade the code would be:

This takes care of all $FACTORY_FOR$ occurences; the files containing other attributes to rename can be found with grep -R FACTORY.

5.8.9 2.4.1 (2014-06-23)

Bugfix:

• Fix overriding deeply inherited attributes (set in one factory, overridden in a subclass, used in a sub-sub-class).

5.8.10 2.4.0 (2014-06-21)

New:

• Add support for factory.fuzzy.FuzzyInteger.step, thanks to ilya-pirogov (issue #120)

5.8. ChangeLog 67

- Add mute_signals() decorator to temporarily disable some signals, thanks to ilya-pirogov (issue #122)
- Add FuzzyFloat (issue #124)
- Declare target model and other non-declaration fields in a class Meta section.

Deprecation:

• Use of FACTORY_FOR and other FACTORY class-level attributes is deprecated and will be removed in 2.5. Those attributes should now declared within the class Meta attribute:

For factory. Factory:

- Rename FACTORY_FOR to model
- Rename ABSTRACT FACTORY to abstract
- Rename FACTORY_STRATEGY to strategy
- Rename FACTORY_ARG_PARAMETERS to inline_args
- Rename FACTORY_HIDDEN_ARGS to exclude

For factory.django.DjangoModelFactory:

- Rename FACTORY_DJANGO_GET_OR_CREATE to django_get_or_create

For factory.alchemy.SQLAlchemyModelFactory:

- Rename FACTORY_SESSION to sqlalchemy_session

5.8.11 2.3.1 (2014-01-22)

Bugfix:

- Fix badly written assert containing state-changing code, spotted by chsigi (issue #126)
- Don't crash when handling objects whose <u>repr</u> is non-pure-ascii bytes on Py2, discovered by mbertheau (issue #123) and strycore (issue #127)

5.8.12 2.3.0 (2013-12-25)

New:

- Add FuzzyText, thanks to jdufresne (issue #97)
- Add FuzzyDecimal, thanks to thedrow (issue #94)
- Add support for EmbeddedDocument, thanks to imiric (issue #100)

5.8.13 2.2.1 (2013-09-24)

Bugfix:

• Fixed sequence counter for <code>DjangoModelFactory</code> when a factory inherits from another factory relating to an abstract model.

5.8.14 2.2.0 (2013-09-24)

Bugfix:

- Removed duplicated SQLA1chemyModelFactory lurking in factory (issue #83)
- Properly handle sequences within object inheritance chains. If FactoryA inherits from FactoryB, and their associated classes share the same link, sequence counters will be shared (issue #93)
- Properly handle nested SubFactory overrides

New:

- The DjangoModelFactory now supports the FACTORY_FOR = 'myapp.MyModel' syntax, making it easier to shove all factories in a single module (issue #66).
- Add factory.debug() helper for easier backtrace analysis
- Adding factory support for mongoengine with MongoEngineFactory.

5.8.15 2.1.2 (2013-08-14)

New:

• The ABSTRACT_FACTORY keyword is now optional, and automatically set to True if neither the Factory subclass nor its parent declare the FACTORY_FOR attribute (issue #74)

5.8.16 2.1.1 (2013-07-02)

Bugfix:

• Properly retrieve the color keyword argument passed to ImageField

5.8.17 2.1.0 (2013-06-26)

New:

- Add FuzzyDate thanks to saulshanabrook
- Add FuzzyDateTime and FuzzyNaiveDateTime.
- Add a factory_parent attribute to the LazyStub passed to LazyAttribute, in order to access fields defined in wrapping factories.
- Move DjangoModelFactory and MogoFactory to their own modules (factory.django and factory.mogo)
- Add the reset_sequence() classmethod to Factory to ease resetting the sequence counter for a given factory.
- Add debug messages to factory logger.
- Add a reset () method to Iterator (issue #63)
- Add support for the SQLAlchemy ORM through SQLAlchemyModelFactory (issue #64, thanks to Romain Commandé)
- Add factory.django.FileField and factory.django.ImageField hooks for related Django model fields (issue #52)

Bugfix

5.8. ChangeLog 69

- Properly handle non-integer pks in D jangoModelFactory (issue #57).
- Disable RelatedFactory generation when a specific value was passed (issue #62, thanks to Gabe Koscky)

Deprecation:

• Rename RelatedFactory's name argument to factory_related_name (See issue #58)

5.8.18 2.0.2 (2013-04-16)

New:

• When FACTORY_DJANGO_GET_OR_CREATE is empty, use Model.objects.create() instead of Model.objects.get_or_create.

5.8.19 2.0.1 (2013-04-16)

New:

• Don't push defaults to get_or_create when FACTORY_DJANGO_GET_OR_CREATE is not set.

5.8.20 2.0.0 (2013-04-15)

New:

- Allow overriding the base factory class for <code>make_factory()</code> and friends.
- Add support for Python3 (Thanks to kmike and nkryptic)
- The default type for Sequence is now int
- Fields listed in FACTORY_HIDDEN_ARGS won't be passed to the associated class' constructor
- Add support for get_or_create in <code>DjangoModelFactory</code>, through <code>FACTORY_DJANGO_GET_OR_CREATE</code>.
- Add support for fuzzy attribute definitions.
- The Sequence counter can be overridden when calling a generating function
- Add Dict and List declarations (Closes issue #18).

Removed:

- Remove associated class discovery
- Remove InfiniteIterator and infinite_iterator()
- Remove CircularSubFactory
- Remove extract_prefix kwarg to post-generation hooks.
- Stop defaulting to Django's Foo.objects.create() when "creating" instances
- Remove STRATEGY *
- Remove set_building_function()/set_creation_function()

5.8.21 1.3.0 (2013-03-11)

Warning: This version deprecates many magic or unexplicit features that will be removed in v2.0.0. Please read the *Upgrading* section, then run your tests with python $-\mathbb{W}$ default to see all remaining warnings.

New

· Global:

- Rewrite the whole documentation
- Provide a dedicated MogoFactory subclass of Factory

• The Factory class:

- Better creation/building customization hooks at factory.Factory._build() and factory.Factory.create()
- Add support for passing non-kwarg parameters to a Factory wrapped class through FACTORY ARG PARAMETERS.
- Keep the FACTORY_FOR attribute in Factory classes

• Declarations:

- Allow SubFactory to solve circular dependencies between factories
- Enhance SelfAttribute to handle "container" attribute fetching
- Add a getter to Iterator declarations
- A Iterator may be prevented from cycling by setting its cycle argument to False
- Allow overriding default arguments in a PostGenerationMethodCall when generating an instance of the factory
- An object created by a DjangoModelFactory will be saved again after PostGeneration hooks execution

Pending deprecation

The following features have been deprecated and will be removed in an upcoming release.

• Declarations:

- InfiniteIterator is deprecated in favor of ${\it Iterator}$
- CircularSubFactory is deprecated in favor of SubFactory
- The extract_prefix argument to post_generation() is now deprecated

• Factory:

- Usage of set_creation_function() and set_building_function() are now deprecated
- Implicit associated class discovery is no longer supported, you must set the FACTORY_FOR attribute on all Factory subclasses

5.8. ChangeLog 71

Upgrading

This version deprecates a few magic or undocumented features. All warnings will turn into errors starting from v2.0.0. In order to upgrade client code, apply the following rules:

- Add a FACTORY_FOR attribute pointing to the target class to each Factory, instead of relying on automagic
 associated class discovery
- When using factory_boy for Django models, have each factory inherit from DjangoModelFactory
- Replace factory.CircularSubFactory('some.module', 'Symbol') with factory.SubFactory('some.module.Symbol')
- Replace factory.InfiniteIterator(iterable) with factory.Iterator(iterable)
- Replace @factory.post_generation() with @factory.post_generation
- Replace factory.set_building_function(SomeFactory, building_function) with an override of the _build() method of SomeFactory
- Replace factory.set_creation_function(SomeFactory, creation_function) with an override of the _create() method of SomeFactory

5.8.22 1.2.0 (2012-09-08)

New:

• Add CircularSubFactory to solve circular dependencies between factories

5.8.23 1.1.5 (2012-07-09)

Bugfix:

• Fix PostGenerationDeclaration and derived classes.

5.8.24 1.1.4 (2012-06-19)

New:

- Add use_strategy() decorator to override a Factory's default strategy
- Improve test running (tox, python2.6/2.7)
- Introduce PostGeneration and RelatedFactory

5.8.25 1.1.3 (2012-03-09)

Bugfix:

· Fix packaging rules

5.8.26 1.1.2 (2012-02-25)

New:

- Add Iterator and InfiniteIterator for Factory attribute declarations.
- Provide generate() and simple_generate(), that allow specifying the instantiation strategy directly. Also provides generate_batch() and simple_generate_batch().

5.8.27 1.1.1 (2012-02-24)

New:

• Add build_batch(), create_batch() and stub_batch(), to instantiate factories in batch

5.8.28 1.1.0 (2012-02-24)

New:

- Improve the SelfAttribute syntax to fetch sub-attributes using the foo.bar syntax;
- Add Container Attribute to fetch attributes from the container of a SubFactory.
- Provide the make_factory() helper: MyClassFactory = make_factory(MyClass, x=3, y=4)
- Add build(), create(), stub() helpers

Bugfix:

· Allow classmethod/staticmethod on factories

Deprecation:

• Auto-discovery of FACTORY_FOR based on class name is now deprecated

5.8.29 1.0.4 (2011-12-21)

New:

- Improve the algorithm for populating a Factory attributes dict
- Add python setup.py test command to run the test suite
- Allow custom build functions
- Introduce MOGO BUILD build function
- Add support for inheriting from multiple Factory
- Base Factory classes can now be declared abstract.
- Provide DjangoModelFactory, whose Sequence counter starts at the next free database id
- Introduce SelfAttribute, a shortcut for factory.LazyAttribute(lambda o: o.foo.bar.baz.

Bugfix:

- Handle nested SubFactory
- Share sequence counter between parent and subclasses

5.8. ChangeLog 73

• Fix SubFactory / Sequence interferences

5.8.30 1.0.2 (2011-05-16)

New:

• Introduce SubFactory

5.8.31 1.0.1 (2011-05-13)

New:

- Allow Factory inheritance
- Improve handling of custom build/create functions

Bugfix:

• Fix concurrency between LazyAttribute and Sequence

5.8.32 1.0.0 (2010-08-22)

New:

• First version of factory_boy

5.8.33 Credits

- Initial version by Mark Sandstrom (2010)
- Developed by Raphaël Barrois since 2011

5.9 Ideas

This is a list of future features that may be incorporated into factory_boy:

- When a Factory is built or created, pass the calling context throughout the calling chain instead of custom solutions everywhere
- Define a proper set of rules for the support of third-party ORMs
- Properly evaluate nested declarations (e.g factory.fuzzy.FuzzyDate(start_date=factory.SelfAttribute('s
- · genindex
- · modindex
- search

Python Module Index

f

factory.fuzzy,58

76 Python Module Index

Symbolsinit() (factory.django.FileField method), 45init() (factory.django.ImageField method), 46adjust_kwargs() (factory.Factory class method), 21after_postgeneration() (factory.Factory class method),22build() (factory.Factory class method), 21create() (factory.Factory class method), 21meta (factory.Factory attribute), 20options_class (factory.Factory attribute), 20setup_next_sequence() (factory.Factory class method),21	dict_factory (factory.Dict attribute), 36 django_get_or_create (factory.django.DjangoOptions attribute), 45 DjangoModelFactory (class in factory.django), 44 DjangoOptions (class in factory.django), 45 E end_date (factory.fuzzy.FuzzyDate attribute), 60 end_dt (factory.fuzzy.FuzzyDateTime attribute), 61 end_dt (factory.fuzzy.FuzzyNaiveDateTime attribute), 62 exclude (factory.FactoryOptions attribute), 19
A abstract (factory.FactoryOptions attribute), 18	Factory (class in factory), 20 factory (factory.RelatedFactory attribute), 38
add_provider() (factory.Faker class method), 26 args (factory.PostGenerationMethodCall attribute), 40	factory.fuzzy (module), 58 FactoryOptions (class in factory), 18
В	Faker (class in factory), 26 FileField (class in factory.django), 45
BaseFuzzyAttribute (class in factory.fuzzy), 62 build() (factory.Factory class method), 20 build() (in module factory), 43	force_day (factory.fuzzy.FuzzyDateTime attribute), 61 force_day (factory.fuzzy.FuzzyNaiveDateTime attribute), 62
build_batch() (factory.Factory class method), 20 build_batch() (in module factory), 43 BUILD_STRATEGY (in module factory), 25	force_flush (factory.alchemy.SQLAlchemyOptions at- tribute), 48 force_hour (factory.fuzzy.FuzzyDateTime attribute), 61
C ,,,	force_hour (factory.fuzzy.FuzzyNaiveDateTime attribute), 62
chars (factory.fuzzy.FuzzyText attribute), 58 choices (factory.fuzzy.FuzzyChoice attribute), 59 create() (factory.Factory class method), 20 create() (in module factory), 43	force_microsecond (factory.fuzzy.FuzzyDateTime attribute), 61 force_microsecond (factory.fuzzy.FuzzyNaiveDateTime attribute), 62 force_minute (factory.fuzzy.FuzzyDateTime attribute), 61
create_batch() (factory.Factory class method), 20 create_batch() (in module factory), 43 CREATE_STRATEGY (in module factory), 25 cycle (factory.Iterator attribute), 34	force_minute (factory.fuzzy.fuzzy.FuzzyNaiveDateTime attribute), 62 force_month (factory.fuzzy.FuzzyDateTime attribute), 61 force_month (factory.fuzzy.FuzzyNaiveDateTime at-
D	tribute), 62
database (factory.django.DjangoOptions attribute), 45 debug() (in module factory), 25 Dict (class in factory), 36	force_second (factory.fuzzy.FuzzyDateTime attribute), 61 force_second (factory.fuzzy.FuzzyNaiveDateTime attribute), 62

force_year (factory.fuzzy.FuzzyDateTime attribute), 61 force_year (factory.fuzzy.FuzzyNaiveDateTime attribute), 62 fuzz() (factory.fuzzy.BaseFuzzyAttribute method), 62 fuzzer (factory.fuzzy.FuzzyAttribute attribute), 58 FuzzyAttribute (class in factory.fuzzy), 58 FuzzyChoice (class in factory.fuzzy), 59 FuzzyDate (class in factory.fuzzy), 60 FuzzyDateTime (class in factory.fuzzy), 60 FuzzyDecimal (class in factory.fuzzy), 59	Meta (factory.Factory attribute), 20 method_name (factory.PostGenerationMethodCall attribute), 40 model (factory.FactoryOptions attribute), 18 MogoFactory (class in factory.mogo), 47 MongoEngineFactory (class in factory.mongoengine), 47 mute_signals() (in module factory.django), 47 N name (factory.RelatedFactory attribute), 38
FuzzyFloat (class in factory.fuzzy), 60 FuzzyInteger (class in factory.fuzzy), 59 FuzzyNaiveDateTime (class in factory.fuzzy), 61 FuzzyText (class in factory.fuzzy), 58	O override_default_locale() (factory.Faker class method), 26
G	Р
generate() (factory.Factory class method), 21 generate() (in module factory), 43 generate_batch() (factory.Factory class method), 21 generate_batch() (in module factory), 43 get_random_state() (in module factory.fuzzy), 62 getter (factory.Iterator attribute), 35	Params (factory.Factory attribute), 20 post_generation() (in module factory), 40 PostGeneration (class in factory), 39 PostGenerationMethodCall (class in factory), 40 precision (factory.fuzzy.FuzzyDecimal attribute), 60 prefix (factory.fuzzy.FuzzyText attribute), 58
Н	R
high (factory.fuzzy.FuzzyDecimal attribute), 60 high (factory.fuzzy.FuzzyFloat attribute), 60 high (factory.fuzzy.FuzzyInteger attribute), 59	RelatedFactory (class in factory), 38 rename (factory.FactoryOptions attribute), 19 reseed_random() (in module factory.fuzzy), 62
I	reset() (factory.Iterator method), 35 reset_sequence() (factory.Factory class method), 22
ImageField (class in factory.django), 46 inline_args (factory.FactoryOptions attribute), 19 Iterator (class in factory), 34 iterator() (in module factory), 35	S SelfAttribute (class in factory), 33 Sequence (class in factory), 28 sequence() (in module factory), 29
K	set_random_state() (in module factory, 22)
kwargs (factory.PostGenerationMethodCall attribute), 40	simple_generate() (factory.Factory class method), 21 simple_generate() (in module factory), 44
L lazy_attribute() (in module factory), 28 lazy_attribute_sequence() (in module factory), 31 LazyAttribute (class in factory), 27 LazyAttributeSequence (class in factory), 30 LazyFunction (class in factory), 27	simple_generate_batch() (factory.Factory class method), 21 simple_generate_batch() (in module factory), 44 sqlalchemy_session (factory.alchemy.SQLAlchemyOptions attribute), 48
length (factory.fuzzy.FuzzyText attribute), 58 List (class in factory), 36	SQLAlchemyModelFactory (class in factory.alchemy), 48
list_factory (factory.List attribute), 37 locale (factory.Faker attribute), 26 low (factory.fuzzy.FuzzyDecimal attribute), 60 low (factory.fuzzy.FuzzyFloat attribute), 60 low (factory.fuzzy.FuzzyInteger attribute), 59	SQLAlchemyOptions (class in factory.alchemy), 48 start_date (factory.fuzzy.FuzzyDate attribute), 60 start_dt (factory.fuzzy.FuzzyDateTime attribute), 61 start_dt (factory.fuzzy.FuzzyNaiveDateTime attribute), 61 step (factory.fuzzy.FuzzyInteger attribute), 59
M	strategy (factory.FactoryOptions attribute), 20 stub() (factory.Factory class method), 21
make_factory() (in module factory) 42	stub() (in module factory), 43

78 Index

```
stub_batch() (factory.Factory class method), 21 stub_batch() (in module factory), 43 STUB_STRATEGY (in module factory), 25 StubFactory (class in factory), 25 StubObject (class in factory), 25 SubFactory (class in factory), 31 suffix (factory.fuzzy.FuzzyText attribute), 58 T
Trait (class in factory), 23
U
use_strategy() (in module factory), 25
```

Index 79